

MICROSOFT WINDOWS 11 23H2

封装教程:不同的系统版本,有着不同的封装方式,封装过程中包含:"语言包:添加、关联、删除"、"驱动:添加、删除"、"累积更新:添加、删除"、"InBox Apps:添加、更新、标记"等。

在这背后藏着很多的隐藏故事, 想解开这些, 你准备好开始这场封装之旅了吗?

摘要

章节1 封装

章节2 报告

章节3 常见问题

章节4 已知问题

章节1	封装					第6页
A.	先决条件			第6页		
	II	ISO工具				第6页
	III	要求				第6页
		1. 系统安	安装包			第6页
		2. 语言包	<u> </u>			
		2.1.	学习			第7页
		2.2.	语言包:下	载		
		2.3.	语言包: 修	缓		第 10 页
		3. InBox A	Apps			第11页
	IV	Windows 安全	è中心			
	V	命令行				第 12 页
В.	语言	包: 提取				第 12 页
	II	语言包: 准备	圣			
	Ш	语言包: 提取	双方案			
	IV	执行提取命令	>			第 13 页
C.	自定	义封装				第19页
	II	自定义封装:	Install.wim			第 19 页
		1. 查看 Ir	nstall.wim 详绰	田信息		第 19 页
		2. 指定挡	挂载 Install 路径	준		第 19 页
		3. 开始挂	圭载 Install.win	1		第 19 页
		3.1.	自定义封装	ቼ: WinRE.wim		第 19 页
			3.1.1.	查看 WinRE.wim 详细信息		第 19 页
			3.1.2.	指定挂载 WinRE.wim 路径		第 19 页

		3.1.3.	开始挂载 WinRE.wim	19页
		3.1.4.	语言包	20页
			3.1.4.1. 语言包:添加	20页
			3.1.4.2. 脱机映像语言: 更改	21页
			3.1.4.2.1. 更改默认语言、区域设置和其他国际设置 第	21页
			3.1.4.2.2. 查看可用的语言设置 第	22页
			3.1.4.3. 语言包: 删除	22页
			3.1.4.4. 组件: 映像中已安装的所有包	24页
		3.1.5.	累积更新	24页
			3.1.5.1. 添加	24页
			3.1.5.2. 删除	25页
			3.1.5.3. 固化更新 第	25页
			3.1.5.3.1. 固化更新后清理组件	25页
		3.1.6.	驱动	25页
		3.1.7.	保存映像:WinRE.wim	25页
		3.1.8.	卸载映像: WinRE.wim	25页
		3.1.9.	重建 WinRE.wim 后,可缩小文件大小 第	25页
		3.1.10.	备份 WinRE.wim 第	26页
		3.1.11.	替换 Install.wim 映像内的 WinRE.wim	26页
4.	语言包			27页
	4.1.	语言包: 汤	添加	27页
	4.2.	脱机映像语	5言: 更改	29页
		4.2.1.	更改默认语言、区域设置和其他国际设置 第	29页
		4.2.2.	查看可用的语言设置	29页

	4.3.	语言包: 删除	第29页
	4.4.	组件:映像中已安装的所有包	第32页
5.	InBox A _l	ops	第32页
	5.1.	学习	第32页
	5.2.	InBox Apps: 预安装应用程序	第32页
	5.3.	InBox Apps:已安装	第34页
	5.4.	删除已安装的所有预应用程序	第34页
	5.5.	区域标记: 了解	第35页
	5.6.	区域标记:添加方式	第35页
	5.7.	InBox Apps:安装	第38页
	5.8.	区域标记: 删除	第47页
	5.9.	InBox Apps:优化	第48页
6.	累积更	新	第48页
	6.1.	专属功能启用包	第48页
	6.2.	初始版本	第49页
	6.3.	其它版本	第50页
	6.4.	固化更新	第50页
		6.4.1. 固化更新后清理组件	第50页
7.	驱动		第51页
8.	部署引	擎:添加	第51页
9.	健康		第51页
10.	替换W	inRE.wim	第51页
11.	保存映	象:Install.wim	第51页
12.		象:Install.wim	
13.		量替换 Install.wim 里的所有索引号里的 WinRE.wim	
	13.1.	获取 WimLib	第51页

		13.2.	如何在 Install.wim 里提取和更新 WinRE.wim	第52页
	1	4. 重建	Install.wim 后可缩小文件大小	第53页
I	∥ É	1定义封装	: boot.wim	第53页
	1.	. 查看	Boot.wim 文件信息	第53页
	2.	. 指定	挂载 Boot.wim 路径	第54页
	3.	. 开始	挂载 Boot.wim	第54页
	4.	. 语言	包	第54页
		4.1.	语言包:添加	第54页
		4.2.	脱机映像语言: 更改	第55页
			4.2.1. 更改默认语言、区域设置和其他国际设置	第55页
			4.2.2. 查看可用的语言设置	第55页
		4.3.	语言包: 删除	第56页
		4.4.	组件:映像中已安装的所有包	第58页
		4.5.	语言包: 修复	第 58 页
		4.6.	语言包:同步到 ISO 安装程序	第59页
		4.7.	重新生成 Lang.ini	第59页
			4.7.1. 重新生成已挂载目录 lang.ini	第59页
			4.7.2. 重新生成 lang.ini 后,同步到安装程序	第59页
	5.	. 累积	更新	第59页
		5.1.	添加	第59页
		5.2.	删除	
		5.3.		第59页
		0.0.	5.3.1. 固化更新后清理组件	第60页
				200页
	6.	. 驱动		第60页

	7. 其它	第60页
	7.1. 绕过 TPM 安装时检查	第60页
	8. 保存映像: Boot.wim	第61页
	9. 卸载映像:Boot.wim	第61页
	IV 部署引擎	第61页
	1. 添加方式	第61页
	2. 部署引擎: 进阶	第64页
D.	ISO	第67页
	II 生成ISO	第67页
	III 绕过 TPM 安装检查	第67页
节2	报告	第68页
II	不同版本	第68页
III	语言安装包适用于: Install.wim	第70页
IV	语言安装包适用于:WinRE.wim	第71页
V	语言安装包适用于:Boot.wim	第73页
节3	常见问题	第74页
II	清理所有挂载到	第74页
Ш	修复挂载出现异常的问题	第74页
IV	清理目录	第74页
节 4	已知问题	第74页

章节1 封装

A. 先决条件

II ISO工具

准备一款可编辑 ISO 文件的软件,例如: PowerISO、DAEMON Tools、ISO Workshop;

Ⅲ 要求

1. 系统安装包

关键词: 迭代、跨版本、大版本、累积更新、初始版本

1.1. 说明

- 1.1.1. 每版本更新时请重新制作镜像,例如从 21H1 跨越到 22H2 时,应避免出现其它兼容性问题请勿在旧镜像基础上制作;
- 1.1.2. 该条例已经在某些 OEM 厂商,通过各种形式向封装师明确传达了该法令,不允许直接从迭代版本里直接升级;
- 1.1.3. 制作中请使用"初始版本"、"开发者版"制作。微软官方文档里曾短暂的出现过在制作中必须使用初始版本,后来这句在官方文档里却被删除了;
- 1.1.4. 安装语言包后,必须重新添加累积更新(可同一版本号),不添加累积更新会出现"乱码"、"界面闪退"等问题。
- 1.1.5. 进化过程: Windows 11 23H2, Build 22631.2428 + KB5031455 = OS Build 22631.2506

1.2. 准备下载初始版本或开发者版本

- 1.2.1. x64
 - **1.2.1.1.** en-us_windows_11_business_editions_version_23h2_x64_dvd_a9092734.iso
 - $\textbf{1.2.1.2.} \qquad \quad \text{en-us_windows_11_consumer_editions_version_23h2_x64_dvd_8ea907fb.iso}$
 - **1.2.1.3.** en-us_windows_11_iot_enterprise_version_23h2_x64_dvd_fb37549c.iso
- 1.2.2. arm64
 - **1.2.2.1.** en-us_windows_11_iot_enterprise_version_23h2_arm64_dvd_6cc52d75.iso
- 1.3. 示例下载 en-us_windows_11_business_editions_version_23h2_x64_dvd_a9092734.iso 后,解压到: D:\en-us_windows_11_business_editions_version_23h2_x64_dvd_a9092734

注意:解压到 D 盘前,你应该检查是否 ReFS 分区格式,如果是 ReFS 分区格式时:执行部分命令将出现异常。解决方法:请使用 NTFS 格式的磁盘分区。

1.4. 解压完成后,将目录 en-us_windows_11_business_editions_version_23h2_x64_dvd_a9092734 更改为 D:\OS_11

- 1.5. 所有脚本、所有路径,已默认设置为 D:\OS_11 为映像来源。
- 1.6. 安装配置
 - 1.6.1. 学习: Windows 安装版配置和产品 ID 文件 (El.cfg 和 PID.txt)
 - 1.6.2. 已知问题
 - 1.6.2.1. 没有 Ei.cfg 时,ISO 引导安装,选择某些版本时会报错,提示: Windows 找不到 Microsoft 软件许可条款。 请确保安装源有效。然后重新启动安装。
 - 1.6.2.2. 如何解决,添加 ei.cfg 到 D:\OS_11\Sources 里,创建 ei.cfg:

@"

[Channel]

volume

[VL]

1

"@ | Out-File -FilePath "D:\OS_11\sources\EI.CFG" -Encoding Ascii

1.7. 报告

查看映像包里已安装:语言包、已关联的语言包组件、预安装 InBox Apps 应用程序等详细信息,下载报告后,使用 Excel 软件打开 .xlsx。

1.7.1. 报告:总览

包含: ISO 系统安装包、映像版本、区域、区域关联、已关联的语言包组件等。

Report.Overview.xlsx

1.7.2. 报告:完整

包容: ISO 系统安装包、映像版本、区域、区域关联、已关联的语言包组件、已安装 InBox Apps 预安装应用程序等。 en-us、ar-sa、bg-bg、cs-cz、da-dk、de-de、el-gr、en-gb、es-es、es-mx、et-ee、fi-fi、fr-ca、fr-fr、he-il、hr-hr、hu-hu、it-it、ja-jp、ko-kr、lt-lt、lv-lv、nb-no、nl-nl、pl-pl、pt-br、pt-pt、ro-ro、ru-ru、sk-sk、sl-si、sr-latn-rs、sv-se、th-th、tr-tr、uk-ua、zh-cn、zh-tw

- 2. 语言包
 - 2.1. 学习

阅读时,请了解"蓝色"重要突出部分。

- 2.1.1. 语言概述
- 2.1.2. 将语言添加到 Windows 11 映像
- 2.1.3. 语言和区域按需功能 (FOD)

2.1.3.1. 字体

- 添加语言包时,触发了对应的区域时,需添加所需的字体功能,下载"所有可用语言 FOD 的列表"了解更多。
- 在"语言包:提取"时,已加入自动识别功能,可了解函数:Function Match_Required_Fonts

2.1.3.2. 区域关联

区域关联是什么?

映像语言仅英文版时,添加 zh-HK 语言包后,映像语言不会新增,应先安装 zh-TW 后,再安装 zh-HK 即可获得对应的关联。

已知区域关联:

- 2.1.3.2.1. 区域: ar-sa, 可选关联区域: en-US, 关联安装包:
 - 2.1.3.2.1.1. Microsoft-Windows-LanguageFeatures-Basic-es-us-

Package~31bf3856ad364e35~amd64~~.cab

- 2.1.3.2.1.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.2. 区域: bg-bg, 可选关联区域: en-US, 关联安装包:
 - 2.1.3.2.2.1. Microsoft-Windows-LanguageFeatures-Basic-es-us-Package~31bf3856ad364e35~amd64~~.cab
 - 2.1.3.2.2.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.3. 区域: da-dk, 可选关联区域: en-US, 关联安装包:
 - 2.1.3.2.3.1. Microsoft-Windows-LanguageFeatures-Basic-es-us-
 - Package~31bf3856ad364e35~amd64~~.cab
 - 2.1.3.2.3.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.4. 区域: el-gr, 可选关联区域: en-US, 关联安装包:
 - 2.1.3.2.4.1. Microsoft-Windows-LanguageFeatures-Basic-es-us-Package~31bf3856ad364e35~amd64~~.cab



- 2.1.3.2.4.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.5. 区域: fr-ca, 可选关联区域: en-US、fr-fr, 关联安装包:
 - 2.1.3.2.5.1. Microsoft-Windows-LanguageFeatures-Basic-es-us-Package~31bf3856ad364e35~amd64~~.cab
 - 2.1.3.2.5.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
 - 2.1.3.2.5.3. Microsoft-Windows-LanguageFeatures-Basic-fr-fr-Package~31bf3856ad364e35~amd64~~.cab
 - 2.1.3.2.5.4. Microsoft-Windows-LanguageFeatures-Handwriting-fi-fi-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.6. 区域: he-il, 可选关联区域: en-US, 关联安装包:
 - 2.1.3.2.6.1. Microsoft-Windows-LanguageFeatures-Basic-es-us-Package~31bf3856ad364e35~amd64~~.cab
 - 2.1.3.2.6.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.7. 区域: ru-ru, 可选关联区域: en-US, 关联安装包:
 - 2.1.3.2.7.1. Microsoft-Windows-LanguageFeatures-Basic-es-us-Package~31bf3856ad364e35~amd64~~.cab
 - 2.1.3.2.7.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.8. 区域: th-th, 可选关联区域: en-US, 关联安装包:
 - $2.1.3.2.8.1. \\ Microsoft-Windows-LanguageFeatures-Basic-es-us-Package~31bf3856ad364e35~amd64~~.cab$
 - 2.1.3.2.8.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.9. 区域: uk-ua, 可选关联区域: en-US, 关联安装包:
 - 2.1.3.2.9.1. Microsoft-Windows-LanguageFeatures-Basic-es-us-Package~31bf3856ad364e35~amd64~~.cab
 - 2.1.3.2.9.2. Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~.cab
- 2.1.3.2.10. 区域: zh-TW, 可选关联区域: zh-HK, 关联安装包:
 - 2.1.3.2.10.1. Microsoft-Windows-LanguageFeatures-Basic-zh-hk-Package~31bf3856ad364e35~amd64~~.cab

2.1.3.2.10.2. Microsoft-Windows-LanguageFeatures-Speech-zh-hk-

Package~31bf3856ad364e35~amd64~~.cab

2.1.3.2.10.3. Microsoft-Windows-LanguageFeatures-TextToSpeech-zh-hk-

Package~31bf3856ad364e35~amd64~~.cab

2.1.3.3. 其它区域特定的要求

触发已知区域时,需添加特定的"程序包"。

历的任何 API 调用失败。

2.1.3.3.1. 区域: zh-TW,程序包: Microsoft-Windows-InternationalFeatures-Taiwan-

Package~31bf3856ad364e35~amd64~~.cab

说明:对台湾日期格式设置要求的补充支持。将为位于台湾的客户提供包。

建议:仅在运送到台湾市场的设备上预安装。 未在设备上安装此功能会导致对使用台湾日

存在争议:

- 在测试中发现,微软官方原版 Windows 11 里并未发现映像里安装此程序包,但是在建议项里有已知问题,到底是遵循与微软官方原版一致,由封装师自由选择安装与否。
- 2.2. 语言包: 下载

 $https://software-static.download.prss.microsoft.com/dbazure/988969d5-f34g-4e03-ac9d-1f9786c66749/22621.2501.231009-1937.ni_release_svc_prod3_amd64fre_InboxApps.iso$

- 2.3. 语言包: 修复
 - 2.3.1. 任选一个网站并打开:
 - 2.3.1.1. https://uupdump.net
 - 2.3.1.2. https://uup.ee
 - 2.3.1.3. https://osdump.com
 - **2.3.2.** 打开后,搜索关键词:22631.2428,在搜索结果选择:Windows 11, version 23H2 (22631.2428) amd64
 - 2.3.3. 打开后,选择"全部文件";
 - 2.3.4. 在"全部文件"页面里依次搜索绿色部分并下载:
 - 2.3.4.1. 适用于: Install.wim (1项)
 - 2.3.4.1.1. MediaPlayer

- 2.3.4.2. 适用于: WinRE.wim, 暂无
- 2.3.4.3. 适用于: Boot.wim, 暂无
- 2.3.5. 下载所有文件后,拉动到页面下方,下载并运行"生成重命名脚本 (Windows)";
- **2.3.6.** 使用 ISO 编辑软件,编辑 22621.2501.231009-1937.ni_release_svc_prod3_amd64fre_InboxApps.iso,将下载的文件添加到 [ISO]:\LanguagesAndOptionalFeatures 目录里;

3. InBox Apps

- 3.1. 下载: https://software-static.download.prss.microsoft.com/dbazure/888969d5-f34g-4e03-ac9d-1f9786c66749/22621.2501.231009-1937.ni_release_svc_prod3_amd64fre_InboxApps.iso
- 3.2. 下载: https://software-static.download.prss.microsoft.com/dbazure/988969d5-f34g-4e03-ac9d-1f9786c66749/22621.1.220506-1250.ni_release_amd64fre_InboxApps.iso 后,提取:
 - 3.2.1. Microsoft.HEVCVideoExtension
 - 3.2.1.1. Microsoft.HEVCVideoExtension_8wekyb3d8bbwe.arm64.appx
 - 3.2.1.2. Microsoft.HEVCVideoExtension_8wekyb3d8bbwe.arm64.xml
 - 3.2.1.3. Microsoft.HEVCVideoExtension_8wekyb3d8bbwe.x64.appx
 - 3.2.1.4. Microsoft.HEVCVideoExtension_8wekyb3d8bbwe.x64.xml
 - 3.2.2. Microsoft.WindowsTerminal
 - ${\bf 3.2.2.1.} \qquad {\bf Microsoft. Windows Terminal_8 we kyb3d8bbwe. msix bundle}$
 - 3.2.2.2. Microsoft.WindowsTerminal_8wekyb3d8bbwe.xml

警告

- 22621.1778.230511-2102.ni_release_svc_prod3_amd64fre_InboxApps.iso 文件里提供的
 Microsoft.WindowsTerminal_8wekyb3d8bbwe.msixbundle 安装版本号是: 1.17.12191, 安装此版本号后无法正常运行。
- Windows 11 23H2 22631.2428 初始版本里提供的版本号是:1.12.10983,安装此版本号可正常运行。
- 3.3. 使用 ISO 编辑工具,编辑 22621.1778.230511-2102.ni_release_svc_prod3_amd64fre_InboxApps.iso,将已提取文件添加到 [ISO]:\packages 目录里;

IV Windows 安全中心

- 在处理封装任务时,将产生大量的临时文件,安装 InBox Apps 里的应用时会释放大量的安装文件;
- 开启 Windows 安全中心会扫描文件、会占用大量的 CPU。

• 测试中:未关闭前耗时1小时22分,关闭后耗时20分钟。

如何关闭:

绿色为命令行,按住 Windows 键并按 R 键启动"运行"。

- 1. 打开"Windows 安全中心"或运行: windowsdefender:
- 2. 选择"病毒和威胁防护"或运行: windowsdefender://threat
- 3. 找到"病毒和威胁防护设置",点击"管理设置"或运行:windowsdefender://threatsettings,建议您关闭部分功能:
 - 3.1. 实时保护
 - 3.2. 云提供的保护
 - 3.3. 自动提交样本
 - 3.4. 篡改防护
- 4. 未处于封装时,建议您开启 Windows 安全中心。

V 命令行

- 1. 可选"Terminal"或"PowerShell ISE",未安装"Terminal",请前往 https://github.com/microsoft/terminal/releases 后下载;
- 2. 以管理员身份打开"Terminal"或"PowerShell ISE",设置 PowerShell 执行策略:绕过,PS 命令行:

Set-ExecutionPolicy -ExecutionPolicy Bypass -Force

- 3. 在本文中,绿色部分属于 PS 命令行,请复制后,粘贴到"Terminal"对话框,按回车键(Enter)后开始运行;
- 4. 有 .ps1 时,点击文件右键,选择以 PowerShell 运行,或复制路径,粘贴到"Terminal"或"PowerShell ISE"里运行,带冒号的路径,在命令 行添加 & 字符,示例:& "D:\YiSolutions_Encapsulation_SIP.ps1"
- B. 语言包: 提取
 - Ⅱ 语言包:准备

挂载 22621.2501.231009-1937.ni_release_svc_prod3_amd64fre_InboxApps.iso 或解压到任意位置;

- Ⅲ 语言包:提取方案
 - 1. 添加
 - 1.1. 语言名称:简体中文-中国,区域:zh-CN,适用范围:Install.Wim, Boot.Wim, WinRE.Wim

Yi's Solutions

2. 删除

2.1. 语言名称: 英语-美国,区域: en-US,适用范围: Install.Wim, Boot.Wim, WinRE.Wim

IV 执行提取命令

- Auto = 自动搜索本地所有磁盘, 默认;
- 自定义路径,例如指定为 E 盘: \$ISO = "E:\"
- Extract.ps1
 - o \Expand\Extract.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Extract.ps1
- 复制代码

```
$ISO = "Auto"
$SaveTo = "D:\OS_11_Custom"
$Extract_language_Pack = @(
    @{ Tag = "zh-CN"; Act = "Add"; Scope = @( "Install\Install"; "Install\WinRE"; "Boot\Boot" ) }
    @{Tag = "en-US"; Act = "Del"; Scope = @( "Install\Install"; "Install\WinRE"; "Boot\Boot" ) }
Function Extract_Language
    param( $Act, $NewLang, $Expand )
    Function Match_Required_Fonts
        param($Lang)
        $Fonts = @(
            @{ Match = @("as", "ar-SA", "ar", "ar-AE", "ar-BH", "ar-DJ", "ar-DZ", "ar-EG", "ar-ER", "ar-IL", "ar-IQ", "ar-JO", "ar-KM", "ar-KW", "ar-LB", "ar-LY", "ar-MA",
"ar-MR", "ar-OM", "ar-PS", "ar-QA", "ar-SD", "ar-SO", "ar-SS", "ar-SY", "ar-TD", "ar-TN", "ar-YE", "arz-Arab", "ckb-Arab", "fa", "fa-AF", "fa-IR", "glk-Arab", "ha-
Arab", "ks-Arab", "ks-Arab-IN", "ku-Arab", "prs-Arab", "pa-Arab-PK", "pnb-Arab", "prs-AF", "prs-AF", "prs-Arab", "ps-AF", "sd-Arab", "ps-Arab", "ps-Arab",
Arab", "sd-Arab-PK", "tk-Arab", "ug", "ug-Arab", "ug-CN", "ur", "ur-IN", "ur-PK", "uz-Arab", "uz-Arab-AF"); Name = "Arab"; }
             @{ Match = @("bn-IN", "as-IN", "bn", "bn-BD", "bpy-Beng"); Name = "Beng"; }
             @{ Match = @("da-dk", "iu-Cans", "iu-Cans-CA"); Name = "Cans"; }
             @{Match = @("chr-Cher-US", "chr-Cher"); Name = "Cher"; }
             @{ Match = @("hi-IN", "bh-Deva", "brx", "brx-Deva", "birx-IN", "hi", "ks-Deva", "mai", "mr", "mr-IN", "ne-IN", "ne-NP", "ne-NP", "new-Deva", "pi-Deva", "sa",
@{ Match = @("am", "am-ET", "byn", "byn-ER", "ti-ER", "ti-ER", "tig-ER", "tig-ER", "tig-Ethi", "ve-Ethi", "wal-Ethi"); Name =
"Ethi"; }
```

```
@{ Match = @("gu", "gu-IN"); Name = "Gujr"; }
             @{ Match = @("pa", "pa-IN", "pa-Guru"); Name = "Guru"; }
             @{\text{Match} = @("zh-CN", "cmn-Hans", "gan-Hans", "hak-Hans", "yue-Hans", "zh-gan-Hans", "zh-hak-Hans", "zh-hak
Hans", "zh-yue-Hans"); Name = "Hans"; }
             @{ Match = @("zh-TW", "cmn-Hant", "hak-Hant", "lzh-Hant", "zh-hak-Hant", "zh-Hant", "zh-HK", "zh-HK", "zh-Hant", "zh-MO", "zh-yue-Hant"); Name =
"Hant"; }
             @{ Match = @("he", "he-IL", "yi"); Name = "Hebr"; }
             @{ Match = @("ja", "ja-JP"); Name = "Jpan"; }
             @{ Match = @("km", "km-KH"); Name = "Khmr"; }
             @{ Match = @("kn", "kn-IN"); Name = "Knda"; }
             @{ Match = @("ko", "ko-KR"); Name = "Kore"; }
             @{ Match = @("de-de", "lo", "lo-LA"); Name = "Laoo"; }
             @{Match = @("ml", "ml-IN"); Name = "Mlym"; }
             @{ Match = @("or", "or-IN"); Name = "Orya"; }
             @{ Match = @("si", "si-LK"); Name = "Sinh"; }
             @{ Match = @("tr-tr", "arc-Syrc", "syr", "syr-SY", "syr-Syrc"); Name = "Syrc"; }
             @{ Match = @("ta", "ta-IN", "ta-LK", "ta-MY", "ta-SG"); Name = "Taml"; }
             @{ Match = @("te", "te-IN"); Name = "Telu"; }
             @{ Match = @("th", "th-TH"); Name = "Thai"; }
         ForEach ($item in $Fonts) {
            if (($item.Match) -Contains $Lang) {
                 return $item.Name
        return "Not_matched"
    Function Match_Other_Region_Specific_Requirements
        param($Lang)
         $RegionSpecific = @(
            @{ Match = @("zh-TW"); Name = "Taiwan"; }
        ForEach ($item in $RegionSpecific) {
```

if ((\$item.Match) -Contains \$Lang) {

```
return $item.Name
 return "Skip_specific_packages"
Function Extract_Process
 param( $Package, $Name, $NewSaveTo )
  \ensuremath{$NewSaveTo}\ = "$($SaveTo)\$($NewSaveTo)\Language\$($Act)\$($NewLang)"
 New-Item -Path $NewSaveTo -ItemType Directory -ErrorAction SilentlyContinue | Out-Null
 if ($ISO -eq "Auto") {
   Get-PSDrive -PSProvider FileSystem -ErrorAction SilentlyContinue | ForEach-Object {
     ForEach ($item in $Package) {
       $TempFilePath = Join-Path -Path $_.Root -ChildPath $item -ErrorAction SilentlyContinue
       if (Test-Path $TempFilePath -PathType Leaf) {
         Write-host "`n Find: " -NoNewLine; Write-host $TempFilePath -ForegroundColor Green
         Write-host " Copy to: " -NoNewLine; Write-host $NewSaveTo
         Copy-Item -Path $TempFilePath -Destination $NewSaveTo -Force
 } else {
   ForEach ($item in $Package) {
     $TempFilePath = Join-Path +Path $ISO - ChildPath $item - ErrorAction SilentlyContinue
     Write-host "`n Find: " -NoNewline; Write-host $TempFilePath -ForegroundColor Green
     if (Test-Path $TempFilePath -PathType Leaf) {
       Write-host " Copy to: " -NoNewLine; Write-host $NewSaveTo
       {\bf Copy-Item\ -Path\ \$TempFilePath\ -Destination\ \$NewSaveTo\ -Force}
     } else {
       Write-host " Not found"
 Write-host "`n Verify the language pack file"
```

```
ForEach ($item in $Package) {
        $Path = "$($NewSaveTo)\$([IO.Path]::GetFileName($item))"
        if (Test-Path $Path -PathType Leaf) {
            Write-host " Discover: " -NoNewLine; Write-host $Path -ForegroundColor Green
        } else {
            Write-host " Not found: " -NoNewLine; Write-host $Path -ForegroundColor Red
$AdvLanguage = @(
    @{
        Path = "Install\Install"
        Rule = @(
             "LanguagesAndOptionalFeatures\Microsoft-Windows-LanguageFeatures-Fonts-{DiyLang}-Package~31bf3856ad364e35~AMD64~~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-Client-Language-Pack_x64_{Lang}.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-LanguageFeatures-Basic-{Lang}-Package~31bf3856ad364e35~AMD64~~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-LanguageFeatures-Handwriting-{Lang}-Package~31bf3856ad364e35~AMD64~~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-LanguageFeatures-OCR-{Lang}-Package~31bf3856ad364e35~AMD64~~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-LanguageFeatures-Speech-{Lang}-Package~31bf3856ad364e35~AMD64~~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-LanguageFeatures-TextToSpeech-{Lang}-Package~31bf3856ad364e35~AMD64~~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-InternetExplorer-Optional-Package~31bf3856ad364e35~AMD64~{Lang}~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~AMD64~{Lang}~.cab"
             "Languages And Optional Features \verb|\Microsoft-Windows-Notepad-System-FoD-Package \verb|\algoes|| 31bf3856ad364e35 \verb|\ww64 \verb|\algoes|| 4angles \verb|\alg
             "LanguagesAndOptionalFeatures\Microsoft-Windows-MediaPlayer-Package-AMD64-{Lang}.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-MediaPlayer-Package-wow64-{Lang}.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~AMD64~{Lang}~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~wow64~{Lang}~.cab"
              "LanguagesAndOptionalFeatures\Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~AMD64~{Lang}~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~AMD64~{Lang}~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~wow64~{Lang}~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~AMD64~{Lang}~.cab"
             "Languages And Optional Features \verb|\Microsoft-Windows-WMIC-FoD-Package-31bf3856ad364e35-wow64-{Lang}-.cab|" and the control of the control 
             "LanguagesAndOptionalFeatures\Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~AMD64~{Lang}~.cab"
             "LanguagesAndOptionalFeatures\Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~{Lang}~.cab"
```

```
"LanguagesAndOptionalFeatures\Microsoft-Windows-InternationalFeatures-{Specific}-Package~31bf3856ad364e35~amd64~~.cab"
@{
 Path = "Install\WinRE"
 Rule = @(
  "Windows Preinstallation Environment\x64\WinPE_OCs\WinPE-FontSupport-{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\lp.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-securestartup_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-atbroker_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-audiocore_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-audiodrivers_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-narrator_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-speech-tts_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-srh_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-srt_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-wds-tools_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-wmi_{Lang}.cab"
   "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-appxdeployment_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-appxpackaging_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-storagewmi_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-wifi_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-rejuv_{Lang}.cab"
  "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-opcservices_{Lang}.cab"
   @{
 Path = "Boot\Boot"
 Rule = @(
```

"Windows Preinstallation Environment\x64\WinPE_OCs\WinPE-FontSupport-{Lang}.cab"



```
"Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\lp.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang\\WinPE-Setup_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\WINPE-SETUP-CLIENT_{Lang}.CAB"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-securestartup_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-atbroker_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-audiodrivers_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-enhancedstorage_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-narrator_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-scripting_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-speech-tts_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-wds-tools_{Lang}.cab"
    "Windows Preinstallation Environment\x64\WinPE_OCs\{Lang}\winpe-wmi_{Lang}.cab"
$NewFonts = Match_Required_Fonts -Lang $NewLang
$SpecificPackage = Match_Other_Region_Specific_Requirements -Lang $NewLang
Foreach ($item in $Expand) {
 $Language = @()
 Foreach ($itemList in $AdvLanguage) {
  if ($itemList.Path -eq $item) {
    Foreach ($PrintLang in $itemList.Rule) {
      $Language += "$($PrintLang)".Replace("{Lang}", $NewLang).Replace("{DiyLang}", $NewFonts).Replace("{Specific}", $SpecificPackage)
    Extract_Process -NewSaveTo $itemList.Path -Package $Language -Name $item
```

ForEach (\$item in \$Extract_language_Pack) { Extract_Language -Act \$item.Act -NewLang \$item.Tag -Expand \$item.Scope }

C. 自定义封装

II 自定义封装: Install.wim

1. 查看 Install.wim 详细信息

映像名称、映像描述、映像大小、架构、版本、索引号等;

\$ViewFile = "D:\OS_11\Sources\Install.wim"

Get-WindowsImage -ImagePath \$ViewFile | Foreach-Object { Get-WindowsImage -ImagePath \$ViewFile -index \$_.ImageIndex }

循环操作区域,开始,

2. 指定挂载 Install 路径

 $New-Item-Path "D: \OS_11_Custom \\Install \\Mount"-ItemType directory-ea Silently \\Continue \\Install \\Contin$

3. 开始挂载 Install.wim

默认索引号: 1

Mount-WindowsImage -ImagePath "D:\OS_11\sources\install\mum" -Index "1" -Path "D:\OS_11_Custom\Install\Install\Mount"

处理 Install.wim 映像内的文件,可选项,开始,

3.1. 自定义封装: WinRE.wim

注意:

- WinRE.wim 属于 Install.wim 映像内的文件;
- Install.wim 有多个索引号时,仅处理任意一个 WinRE.wim 即可;
- 同步至所有索引号即可减少 Install.wim 体积,学习"如何批量替换 Install.wim 里的所有索引号里的 WinRE.wim"。
- 3.1.1. 查看 WinRE.wim 详细信息

映像名称、映像描述、映像大小、架构、版本、索引号等;

 $\label{thm:local_local_local} $$ \text{ViewFile} = "D:\OS_11_Custom\Install\Install\Mount\Windows\System32\Recovery\WinRE.wim"} $$$

Get-WindowsImage -ImagePath \$ViewFile | Foreach-Object { Get-WindowsImage -ImagePath \$ViewFile -index \$_.ImageIndex }

3.1.2. 指定挂载 WinRE.wim 路径

New-Item -Path "D:\OS_11_Custom\Install\WinRE\Mount" -ItemType directory -ea SilentlyContinue

3.1.3. 开始挂载 WinRE.wim



默认索引号: 1

3.1.4. 语言包

- 自动安装语言包:获取"组件:映像中已安装的所有包"后进行匹配,匹配到对应的名称后,再安装本地对应的语言包文件,查看报告"语言安装包适用于WinRE.wim"。
- 添加语言时,须对应不同的架构版本,未对应时,添加过程中报错等提示。

3.1.4.1. 语言包:添加

- WinRE.Instl.lang.ps1
 - o \Expand\Install\WinRE\WinRE.Instl.lang.ps1
 - https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Inst all/WinRE/WinRE.Instl.lang.ps1

• 复制代码

```
$Mount = "D:\OS_11_Custom\Install\WinRE\Mount"
$Sources = "D:\OS_11_Custom\Install\WinRE\Language\Add\zh-CN"
$Initl_install_Language_Component = @()
Get-WindowsPackage -Path $Mount | ForEach-Object {
 $Initl_install_Language_Component += $_.PackageName
Add-WindowsPackage -Path $Mount -PackagePath "$($Sources)\WinPE-FontSupport-zh-CN.cab"
$Language_List = @(
 @{ Match = "*WinPE-LanguagePack-Package*"; File = "lp.cab"; }
 @{ Match = "*SecureStartup*"; File = "winpe-securestartup_zh-CN.cab"; }
 @{ Match = "*ATBroker*"; File = "winpe-atbroker_zh-CN.cab"; }
 @{ Match = "*AudioCore*"; File = "winpe-audiocore_zh-CN.cab"; }
 @{ Match = "*AudioDrivers*"; File = "winpe-audiodrivers_zh-CN.cab"; }
 @{ Match = "*EnhancedStorage*"; File = "winpe-enhancedstorage_zh-CN.cab"; }
 @{ Match = "*Narrator*"; File = "winpe-narrator_zh-CN.cab"; }
 @{ Match = "*scripting*"; File = "winpe-scripting_zh-CN.cab"; }
 @{ Match = "*Speech-TTS*"; File = "winpe-speech-tts_zh-CN.cab"; }
 @{ Match = "*srh*"; File = "winpe-srh_zh-CN.cab"; }
```

```
@{ Match = "*srt*"; File = "winpe-srt_zh-CN.cab"; }
 @{ Match = "*wds-tools*"; File = "winpe-wds-tools_zh-CN.cab"; }
 @{ Match = "*-WMI-Package*"; File = "winpe-wmi_zh-CN.cab"; }
 @{ Match = "*WinPE-AppxPackaging*"; File = "winpe-appxpackaging_zh-CN.cab"; }
 @{ Match = "*StorageWMI*"; File = "winpe-storagewmi_zh-CN.cab"; }
 @{ Match = "*WiFi*"; File = "winpe-wifi_zh-CN.cab"; }
 @{ Match = "*rejuv*"; File = "winpe-rejuv_zh-CN.cab"; }
 @{ Match = "*opcservices*"; File = "winpe-opcservices_zh-CN.cab"; }
 @{ Match = "*hta*"; File = "winpe-hta_zh-CN.cab"; }
 @{ Match = "*windowsupdate*"; File = "winpe-windowsupdate_zh-CN.cab"; }
 @{ Match = "*appxdeployment*"; File = "winpe-appxdeployment_zh-CN.cab"; }
ForEach ($Rule in $Language_List) {
 Write-host "`n Rule name: $($Rule.Match)" -ForegroundColor Yellow; Write-host "$('-' * 80)"
 ForEach ($Component in $Initl_install_Language_Component) {
   if ($Component -like "*$($Rule.Match)*") {
     Write-host " Component name: " -NoNewline
     Write-host $Component -ForegroundColor Green
     Write-host "Language pack file: "-NoNewline
     Write-host "$($Sources)\$($Rule.File)" -ForegroundColor Green
     Write-Host " Installing ".PadRight(22) -NoNewline
     try {
      Add-WindowsPackage -Path $Mount -PackagePath "$($Sources)\$($Rule.File)" | Out-Null
      Write-host "Finish" -ForegroundColor Green
     } catch {
      Write-host "Failed" -ForegroundColor Red
     break
```

3.1.4.2. 脱机映像语言: 更改

3.1.4.2.1. 更改默认语言、区域设置和其他国际设置

3.1.4.2.2. 查看可用的语言设置

Dism /Image:"D:\OS_11_Custom\Install\WinRE\Mount" /Get-Intl

3.1.4.3. 语言包: 删除

- 添加语言后,如果要部署到非英语区域,可通过删除英语语言组件来节省空间。删除语言时, 请按与添加语言组件相反的顺序卸载语言组件。
- 添加中文后,反向删除"英语-美国",区域: en-US,需提前提取语言包
- WinRE.Del.Specified.lang.Tag.ps1
 - o \Expand\Install\WinRE\WinRE.Del.Specified.lang.Tag.ps1
 - https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/In stall/WinRE/WinRE.Del.Specified.lang.Tag.ps1

• 复制代码

```
$Lang = "en-US"
$Mount = "D:\OS_11_Custom\Install\WinRE\Mount"
$Sources = "D:\OS_11_Custom\Install\WinRE\Language\Del\en-US"
$Initl_install_Language_Component = @()
Get-WindowsPackage -Path $Mount | ForEach-Object {
 $Initl_install_Language_Component += $_.PackageName
$Language = @(
 @{ Match = "*windowsupdate*"; File = "winpe-windowsupdate_$($Lang).cab"; }
 @{ Match = "*appxdeployment*"; File = "winpe-appxdeployment_$($Lang).cab"; }
 @{ Match = "*hta*"; File = "winpe-hta_$($Lang).cab"; }
 @{ Match = "*opcservices*"; File = "winpe-opcservices_$($Lang).cab"; }
 @{ Match = "*rejuv*"; File = "winpe-rejuv_$($Lang).cab"; }
 @{ Match = "*WiFi*"; File = "winpe-wifi_$($Lang).cab"; }
 @{ Match = "*StorageWMI*"; File = "winpe-storagewmi_$($Lang).cab"; }
 @{ Match = "*WinPE-AppxPackaging*"; File = "winpe-appxpackaging_$($Lang).cab"; }
 @{ Match = "*-WMI-Package*"; File = "winpe-wmi_$($Lang).cab"; }
 @{ Match = "*wds-tools*"; File = "winpe-wds-tools_$($Lang).cab"; }
```

```
@{ Match = "*srt*"; File = "winpe-srt_$($Lang).cab"; }
 @{ Match = "*srh*"; File = "winpe-srh_$($Lang).cab"; }
 @{ Match = "*Speech-TTS*"; File = "winpe-speech-tts_$($Lang).cab"; }
 @{ Match = "*scripting*"; File = "winpe-scripting_$($Lang).cab"; }
 @{ Match = "*Narrator*"; File = "winpe-narrator_$($Lang).cab"; }
 @{ Match = "*EnhancedStorage*"; File = "winpe-enhancedstorage_$($Lang).cab"; }
 @{ Match = "*AudioDrivers*"; File = "winpe-audiodrivers_$($Lang).cab"; }
 @{ Match = "*AudioCore*"; File = "winpe-audiocore_$($Lang).cab"; }
 @{ Match = "*ATBroker*"; File = "winpe-atbroker_$($Lang).cab"; }
 @{ Match = "*SecureStartup*"; File = "winpe-securestartup_$($Lang).cab"; }
 @{ Match = "*WinPE-LanguagePack-Package*"; File = "lp.cab"; }
ForEach ($Rule in $Language) {
 Write-host "`n Rule name: $($Rule.Match)" -ForegroundColor Yellow; Write-host "$('-' * 80)"
 ForEach ($Component in $Initl_install_Language_Component) {
   if ($Component -like "*$($Rule.Match)*$($Lang)*") {
     Write-host " Component name: " -NoNewline
     Write-host $Component -ForegroundColor Green
     Write-host "Language pack file: "-NoNewline
     Write-host "$($Sources)\$($Rule.File)" -ForegroundColor Green
     Write-Host " Deleting ".PadRight(22) -NoNewline
     try {
      Remove-WindowsPackage -Path $Mount -PackagePath "$($Sources)\$($Rule.File)" -ErrorAction
SilentlyContinue | Out-Null
      Write-host "Finish" -ForegroundColor Green
     } catch {
      Write-host "Failed" -ForegroundColor Red
      Write-host " $($_)" -ForegroundColor Red
     break
$InitlClearLanguagePackage = @()
Get-WindowsPackage -Path $Mount | ForEach-Object {
```

3.1.4.4. 组件:映像中已安装的所有包

3.1.4.4.1. 查看

 ${\tt Get-WindowsPackage-Path~"D:\NOS_11_Custom\Install\WinRE\Mount"~|~Out-GridView}$

3.1.4.4.2. 导出到 Csv

\$SaveTo = "D:\OS_11_Custom\Install\WinRE\Report.\$(Get-Date -Format "yyyyMMddHHmmss").csv"

Get-WindowsPackage -Path "D:\OS_11_Custom\Install\WinRE\Mount" | Export-CSV -NoType -Path \$SaveTo

Write-host \$SaveTo -ForegroundColor Green

3.1.5. 累积更新

准备可用的累积更新文件,请更改示例文件名: KB_WinRE.cab

3.1.5.1. 添加

 $$KBPath = "D:\OS_11_Custom\Install\WinRE\Update\KB_WinRE.cab"$



3.1.5.2. 删除

\$KBPath = "D:\OS_11_Custom\Install\WinRE\Update\KB_WinRE.cab"

3.1.5.3. 固化更新

固化后不可卸载,固化时将清理恢复映像并重置任何被取代的组件的基础。

 $\label{lem:limit} \begin{tabular}{ll} $$ Dism/image:"D:\OS_11_Custom\Install\WinRE\Mount"/cleanup-image/StartComponentCleanup/ResetBase \end{tabular} $$ All $$ A$

3.1.5.3.1. 固化更新后清理组件

```
$Mount = "D:\OS_11_Custom\Install\WinRE\Mount"

Get-WindowsPackage -Path $Mount -ErrorAction SilentlyContinue | ForEach-Object {

if ($_.PackageState -eq "Superseded") {

Write-Host " $($_.PackageName)" -ForegroundColor Green
```

Remove-WindowsPackage -Path \$Mount -PackageName \$_.PackageName | Out-Null

}

3.1.6. 驱动

3.1.7. 保存映像: WinRE.wim

 $Save-WindowsImage - Path "D: \OS_11_Custom \Install \WinRE \Mount"$

3.1.8. 卸载映像: WinRE.wim

关闭所有可能正在访问映像中文件的应用程序,包括文件资源管理器。

 $\label{thm:loss} Dismount-Windows Image - Path "D:\OS_11_Custom\\Install\\\WinRE\\\Mount" - Discard$

3.1.9. 重建 WinRE.wim 后,可缩小文件大小

- WinRE.Rebuild.ps1
 - o \Expand\Install\WinRE\WinRE.Rebuild.ps1
 - https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install/WinRE/WinRE/WinRE.Rebuild.ps1



• 复制代码

```
FileName = "D:\OS_11\_Custom\Install\Mount\Windows\System32\Recovery\WinRE.wim"
 Get-WindowsImage - ImagePath $Filename - ErrorAction SilentlyContinue | ForEach-Object {
       Write-Host " Image name: " -NoNewline
       Write-Host $_.ImageName -ForegroundColor Yellow
       Write-Host " The index number: "-NoNewline
       Write-Host $_.ImageIndex -ForegroundColor Yellow
       Write-Host "`n Rebuild".PadRight(28) -NoNewline
       Export-Windows Image - Source Image Path \$File name - Source Index \$\_. Image Index - Destination Image Path \$File name - Source Index \$\_. Image Index - Destination Image Path \$File name - Source Index \$\_. Image Index - Destination Image Path \$File name - Source Index \$\_. Image Index - Destination Image Path \$File name - Source Index \$\_. Image Index - Destination Image Path \$File name - Source Index \$\_. Image Index - Destination Image Path Image Index - Destination Image Index - Destination Image Path Image Index - Destination Image Index - Destination Image Index - Destination Image Index - Destination Image Image Index - Destination Image Index - Destination Image Index - Destination Image Image Image Index - Destination Image Im
  "$($FileName).New" -CompressionType max
      Write-Host "Finish`n" -ForegroundColor Green
if (Test-Path "$($FileName).New" -PathType Leaf) {
       Remove-Item -Path $Filename
       Move-Item -Path "$($FileName).New" -Destination $Filename
       Write-Host "Finish" -ForegroundColor Green
} else {
      Write-host "Failed" -ForegroundColor Red
```

3.1.10. 备份 WinRE.wim

- WinRE.Backup.ps1
 - \Expand\Install\WinRE\WinRE.Backup.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install/WinRE/Win RE.Backup.ps1

• 复制代码

```
$WimLibPath = "D:\OS_11_Custom\Install\Install\Update\Winlib"

$FileName = "D:\OS_11_Custom\Install\Install\Mount\Windows\System32\Recovery\WinRE.wim"

New-Item -Path $WimLibPath -ItemType Directory -ea SilentlyContinue

Copy-Item -Path $FileName -Destination $WimLibPath -Force
```

3.1.11. 替换 Install.wim 映像内的 WinRE.wim

• 每次挂载 Install.wim 后"替换 WinRE.wim";

• 学习"获取 Install.wim 所有索引号后并替换旧的 WinRE.wim"。

处理 Install.wim 映像内的文件,结束。

4. 语言包

- 自动安装语言包:获取"组件:映像中已安装的所有包"后进行匹配,匹配到对应的名称后,再安装本地对应的语言包文件,查看报告"语言安装包适用于Install.wim"。
- 添加语言时,须对应不同的架构版本,未对应时,添加过程中报错等提示。

4.1. 语言包:添加

- Install.Instl.lang.ps1
 - o \Expand\Install.Instl.lang.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install.Instl.lang.ps1

• 复制代码

```
$Mount = "D:\OS_11_Custom\Install\Install\Mount"
$Sources = "D:\OS_11_Custom\Install\Install\Language\Add\zh-CN"
$Initl_install_Language_Component = @()
Get-WindowsPackage -Path $Mount | ForEach-Object {
  $Initl_install_Language_Component += $_.PackageName
Add-WindowsPackage -Path $Mount -PackagePath "$($Sources)\Microsoft-Windows-LanguageFeatures-Fonts-Hans-
Package~31bf3856ad364e35~amd64~~.cab"
$Language_List = @(
    @{ Match = "*Client-LanguagePack-Package*"; File = "Microsoft-Windows-Client-Language-Pack_x64_zh-CN.cab"; }
    @{ Match = "*LanguageFeatures-Basic*"; File = "Microsoft-Windows-LanguageFeatures-Basic-zh-CN-
Package~31bf3856ad364e35~amd64~~.cab"; }
    @{ Match = "*Handwriting*"; File = "Microsoft-Windows-LanguageFeatures-Handwriting-zh-CN-
Package~31bf3856ad364e35~amd64~~.cab"; }
    @{ Match = "*OCR*"; File = "Microsoft-Windows-LanguageFeatures-OCR-zh-CN-Package~31bf3856ad364e35~amd64~~.cab"; }
    @{ Match = "*LanguageFeatures-Speech*"; File = "Microsoft-Windows-LanguageFeatures-Speech-zh-CN-
Package~31bf3856ad364e35~amd64~~.cab"; }
    @{ Match = "*TextToSpeech*"; File = "Microsoft-Windows-LanguageFeatures-TextToSpeech-zh-CN-
Package~31bf3856ad364e35~amd64~~.cab"; }
    @\{ Match = "*InternetExplorer*"; File = "Microsoft-Windows-InternetExplorer-Optional-Package~31bf3856ad364e35~AMD64~zh-Defended and the substitution of the substitu
CN~.cab"; }
```

```
@{ Match = "*Notepad*amd64*"; File = "Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~AMD64~zh-
CN~.cab"; }
 @{ Match = "*Notepad*wow64*"; File = "Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~wow64~zh-
CN~.cab"; }
 @{ Match = "*MediaPlayer*amd64*"; File = "Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab"; }
 @{ Match = "*MediaPlayer*wow64*"; File = "Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab"; }
 @{ Match = "*PowerShell*amd64*"; File = "Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~amd64~zh-
CN~.cab"; }
 @{ Match = "*PowerShell*wow64*"; File = "Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~wow64~zh-
CN~.cab"; }
 @{ Match = "*Printing*PMCPPC*amd64*"; File = "Microsoft-Windows-Printing-PMCPPC-FoD-
Package~31bf3856ad364e35~AMD64~zh-CN~.cab"; }
 CN~.cab"; }
 @{ Match = "*StepsRecorder*wow64*"; File = "Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~wow64~zh-
CN~.cab"; }
 @{ Match = "*WMIC*FoD*Package*amd64*"; File = "Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~AMD64~zh-
CN~.cab"; }
 @{ Match = "*WMIC*FoD*Package*wow64*"; File = "Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~wow64~zh-
CN~.cab"; }
 @{ Match = "*WordPad*amd64*"; File = "Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~amd64~zh-CN~.cab"; }
 @{ Match = "*WordPad*wow64*"; File = "Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~zh-CN~.cab"; }
 @{ Match = "*Client*LanguagePack*zh-TW*"; File = "Microsoft-Windows-InternationalFeatures-Taiwan-
Package~31bf3856ad364e35~amd64~~.cab"; }
ForEach ($Rule in $Language_List) {
 Write-host "`n Rule name: $($Rule.Match)" -ForegroundColor Yellow; Write-host "$('-' * 80)"
 ForEach ($Component in $Initl_install_Language_Component) {
  if ($Component -like "*$($Rule.Match)*") {
    Write-host " Component name: " -NoNewline; Write-host $Component -ForegroundColor Green
    Write-host " Language pack file: "-NoNewline; Write-host "$($Sources)\$($Rule.File)" -ForegroundColor Green
    Write-Host " Installing ".PadRight(22) -NoNewline
    try {
      Add-WindowsPackage -Path $Mount -PackagePath "$($Sources)\$($Rule.File)" | Out-Null
      Write-host "Finish" -ForegroundColor Green
    } catch {
      Write-host "Failed" -ForegroundColor Red
```

```
break
}
```

4.2. 脱机映像语言: 更改

- 从 Windows 11 开始,DISM 设置的默认系统 UI 语言在所有版本中保持不变(家庭版除外)。对于所有商业版,在开箱即用体验 (OOBE) 期间选择的语言会设置为系统首选 UI 语言,Windows 将以此语言显示;对于家庭版,在 OOBE 期间选择的语言将继续用作默认系统 UI 语言。
- 从 Windows 10 版本 2004 开始,如果将基于 .appx 的语言体验包 (LXP) 支持的语言作为参数传递,则该语言将设置为系统
 首选 UI 语言,其父语言将设置为默认系统 UI 语言。在以前的版本中,仅支持基于 .cab 的语言包。

4.2.1. 更改默认语言、区域设置和其他国际设置

区域: zh-CN

Dism /Image: "D:\OS_11_Custom\Install\Install\Mount" /Set-AllIntl: "zh-CN"

4.2.2. 查看可用的语言设置

Dism /Image:"D:\OS_11_Custom\Install\Install\Mount" /Get-Intl

4.3. 语言包: 删除

- 添加语言后,如果要部署到非英语区域,可通过删除英语语言组件来节省空间。删除语言时,请按与添加语言组件相反的顺序卸载语言组件。
- 添加中文后,反向删除"英语-美国",区域: en-US,需提前提取语言包
- Install.Del.Specified.lang.Tag.ps1
 - o \Expand\Install\Install.Del.Specified.lang.Tag.ps1
 - https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install/Install.Del.Specified.la
 ng.Tag.ps1

• 复制代码

```
$Lang = "en-US"

$Mount = "D:\OS_11_Custom\Install\Install\Mount"

$Sources = "D:\OS_11_Custom\Install\Install\Language\Del\en-US"

$Initl_install_Language_Component = @()

Get-WindowsPackage -Path $Mount | ForEach-Object {
```

```
$Initl_install_Language_Component += $_.PackageName
$Language = @(
  @{ Match = "*WordPad*wow64*"; File = "Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~$($Lang)~.cab"; }
  @{ Match = "*WordPad*amd64*"; File = "Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~amd64~$($Lang)~.cab"; }
  @{ Match = "*WMIC*FoD*Package*wow64*"; File = "Microsoft-Windows-WMIC-FoD-
Package~31bf3856ad364e35~wow64~$($Lang)~.cab";}
  @{ Match = "*WMIC*FoD*Package*amd64*"; File = "Microsoft-Windows-WMIC-FoD-
Package~31bf3856ad364e35~AMD64~$($Lang)~.cab"; }
  @{ Match = "*StepsRecorder*wow64*"; File = "Microsoft-Windows-StepsRecorder-
Package~31bf3856ad364e35~wow64~$($Lang)~.cab";}
  @{ Match = "*StepsRecorder*amd64*"; File = "Microsoft-Windows-StepsRecorder-
Package~31bf3856ad364e35~amd64~$($Lang)~.cab";}
  @{ Match = "*Printing*PMCPPC*amd64*"; File = "Microsoft-Windows-Printing-PMCPPC-FoD-
Package~31bf3856ad364e35~AMD64~$($Lang)~.cab";}
  @{ Match = "*PowerShell*wow64*"; File = "Microsoft-Windows-PowerShell-ISE-FOD-
Package~31bf3856ad364e35~wow64~$($Lang)~.cab";}
  @{ Match = "*PowerShell*amd64*"; File = "Microsoft-Windows-PowerShell-ISE-FOD-
Package~31bf3856ad364e35~amd64~$($Lang)~.cab";}
  @{ Match = "*MediaPlayer*wow64*"; File = "Microsoft-Windows-MediaPlayer-Package-wow64-$($Lang).cab"; }
  @{ Match = "*MediaPlayer*amd64*"; File = "Microsoft-Windows-MediaPlayer-Package-AMD64-$($Lang).cab"; }
  @{ Match = "*Notepad*wow64*"; File = "Microsoft-Windows-Notepad-System-FoD-
Package~31bf3856ad364e35~wow64~$($Lang)~.cab";}
  @{ Match = "*Notepad*amd64*"; File = "Microsoft-Windows-Notepad-System-FoD-
Package~31bf3856ad364e35~AMD64~$($Lang)~.cab";}
  @{ Match = "*InternetExplorer*"; File = "Microsoft-Windows-InternetExplorer-Optional-
Package~31bf3856ad364e35~AMD64~$($Lang)~.cab"; }
  @{ Match = "*TextToSpeech*"; File = "Microsoft-Windows-LanguageFeatures-TextToSpeech-$($Lang)-
Package~31bf3856ad364e35~amd64~~.cab"; }
  @{ Match = "*LanguageFeatures-Speech*"; File = "Microsoft-Windows-LanguageFeatures-Speech-$($Lang)-
Package~31bf3856ad364e35~amd64~~.cab";}
  @{ Match = "*OCR*"; File = "Microsoft-Windows-LanguageFeatures-OCR-$($Lang)-Package~31bf3856ad364e35~amd64~~.cab"; }
  @\{ Match = "*Handwriting*"; File = "Microsoft-Windows-LanguageFeatures-Handwriting-\$(\$Lang)-1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 10000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 10000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000 + 1000
Package~31bf3856ad364e35~amd64~~.cab"; }
  @{ Match = "*LanguageFeatures-Basic*"; File = "Microsoft-Windows-LanguageFeatures-Basic-$($Lang)-
Package~31bf3856ad364e35~amd64~~.cab"; }
  @{ Match = "*Client-LanguagePack-Package*"; File = "Microsoft-Windows-Client-Language-Pack_x64_$($Lang).cab"; }
ForEach ($Rule in $Language) {
  Write-host "`n Rule name: $($Rule.Match)" -ForegroundColor Yellow; Write-host "$('-' * 80)"
```

```
For Each ($Component in $Initl_install_Language_Component) {
   if ($Component -like "*$($Rule.Match)*$($Lang)*") {
    Write-host " Component name: " -NoNewline; Write-host $Component -ForegroundColor Green
    Write-host " Language pack file: " -NoNewline; Write-host "$($Sources)\$($Rule.File)" -ForegroundColor Green
    Write-Host " Deleting ".PadRight(22) -NoNewline
    try {
      Remove-WindowsPackage -Path $Mount -PackagePath "$($Sources)\$($Rule.File)" -ErrorAction SilentlyContinue | Out-Null
      Write-host "Finish" -ForegroundColor Green
    } catch {
      Write-host "Failed" -ForegroundColor Red
      Write-host " $($_)" -ForegroundColor Red
    break
$InitlClearLanguagePackage = @()
Get-WindowsPackage -Path $Mount | ForEach-Object {
 if ($_.PackageName -like "*$($Lang)*") {
   $InitlClearLanguagePackage += $_.PackageName
if ($InitlClearLanguagePackage.count -gt 0) {
 ForEach ($item in $InitlClearLanguagePackage) {
   Write-Host "`n $($item)" -ForegroundColor Green
   Write-Host " Deleting ".PadRight(22) -NoNewline
   try {
     Write-host "Finish" -ForegroundColor Green
   } catch {
    Write-host "Failed" -ForegroundColor Red
    Write-host " $($_)" -ForegroundColor Red
```

4.4. 组件:映像中已安装的所有包

4.4.1. 查看

 $Get-Windows Package - Path "D: \OS_11_Custom \Install \Install \Mount" \mid Out-Grid View$

4.4.2. 导出到 Csv

\$SaveTo = "D:\OS_11_Custom\Install\Install\Report.\$(Get-Date -Format "yyyyMMddHHmmss").csv"

Get-WindowsPackage -Path "D:\OS_11_Custom\Install\Install\Mount" | Export-CSV -NoType -Path \$SaveTo

Write-host \$SaveTo -ForegroundColor Green

5. InBox Apps

5.1. 学习

5.1.1. DISM 应用包 (.appx 或 .appxbundle) 服务命令行选项

5.2. InBox Apps: 预安装应用程序

编组缩写

- 群组 A: 教育版, 专业版, 专业教育版, 专业版工作站, 企业版, IoT企业版, 适用于虚拟桌面的 Windows 10企业版
- 群组 B:企业版 N,企业版 GN,企业版 SN,专业版 N,教育版 N,专业版工作站 N,专业教育版 N
- 群组 C: 家庭版, 家庭版 N, 家庭单语版

	名称	产品 ID	编组
1.	Microsoft.HEIFImageExtension	9PMMSR1CGPWG	A, C
2.	Microsoft.HEVCVideoExtension	9NMZLZ57R3T7	A, C
3.	Microsoft.VP9VideoExtensions	9N4D0MSMP0PT	A, C
4.	Microsoft.WebpImageExtension	9PG2DK419DRG	A, C
5.	Microsoft.GamingApp	9MV0B5HZVK9Z	A, C
6.	Microsoft.ZuneMusic	9WZDNCRFJ3PT	A, C
7.	MicrosoftCorporationII.MicrosoftFamily	9PDJDJS743XF	С
8.	Microsoft.WebMediaExtensions	9N5TDP8VCMHS	A, C
9.	Microsoft.WindowsSoundRecorder	9WZDNCRFHWKN	A, C
10.	Microsoft.Xbox.TCUI	9NKNC0LD5NN6	A, C
11.	Microsoft.ZuneVideo	9WZDNCRFJ3P2	A, C

12.	Microsoft.XboxGamingOverlay	9NZKPSTSNW4P	A, C
13.	Microsoft.RawImageExtension	9NCTDW2W1BH8	A, C
14.	Microsoft.UI.Xaml.2.3		A, B, C
15.	Microsoft.UI.Xaml.2.4		A, B, C
16.	Microsoft.UI.Xaml.2.7		A, B, C
17.	Microsoft.UI.Xaml.2.8		A, B, C
18.	Microsoft.NET.Native.Framework.2.2		A, B, C
19.	Microsoft.NET.Native.Runtime.2.2		A, B, C
20.	Microsoft.VCLibs.140.00		A, B, C
21.	Microsoft.VCLibs.140.00.UWPDesktop		A, B, C
22.	Microsoft.SecHealthUI	9NK0JLZT7JD0	A, B, C
23.	Microsoft.WindowsStore	9WZDNCRFJBMP	A, B, C
24.	Microsoft.Sticky.Notes	9NBLGGH4QGHW	A, B, C
25.	Microsoft.Paint	9PCFS5B6T72H	A, B, C
26.	Microsoft.PowerAutomateDesktop	9NFTCH6J7FHV	A, B, C
27.	Microsoft.ScreenSketch	9MZ95KL8MR0L	A, B, C
28.	Microsoft.WindowsNotepad	9MSMLRH6LZF3	A, B, C
29.	Microsoft.WindowsTerminal	9N0DX20HK701	A, B, C
30.	Clipchamp.Clipchamp	9P1J8S7CCWWT	A, B, C
31.	Microsoft.Solitaire.Collection	9WZDNCRFHWD2	A, B, C
32.	Microsoft.WindowsAlarms	9WZDNCRFJ3PR	A, B, C
33.	Microsoft.WindowsFeedbackHub	9NBLGGH4R32N	A, B, C
34.	Microsoft.WindowsMaps	9WZDNCRDTBVB	A, B, C
35.	Microsoft.BingNews	9WZDNCRFHVFW	A, B, C
36.	Microsoft.DesktopAppInstaller	9NBLGGH4NNS1	A, B, C
37.	Microsoft.WindowsCamera	9WZDNCRFJBBG	A, B, C
38.	Microsoft.Getstarted	9WZDNCRDTBJJ	A, B, C
39.	Microsoft.Cortana	9NFFX4SZZ23L	A, B, C
40.	Microsoft.BingWeather	9WZDNCRFJ3Q2	A, B, C
41.	Microsoft.GetHelp	9PKDZBMV1H3T	A, B, C
42.	Microsoft.MicrosoftOfficeHub	9WZDNCRD29V9	A, B, C
43.	Microsoft.People	9NBLGGH10PG8	A, B, C
44.	Microsoft.StorePurchaseApp	9NBLGGH4LS1F	A, B, C
45.	Microsoft.Todos	9NBLGGH5R558	A, B, C

46.	Microsoft.Windows.Photos	9WZDNCRFJBH4	A, B, C
47.	Microsoft.WindowsCalculator	9WZDNCRFHVN5	A, B, C
48.	Microsoft.Windows.CommunicationsApps	9WZDNCRFHVQM	A, B, C
49.	Microsoft.XboxGameOverlay	9NBLGGH537C2	A, B, C
50.	Microsoft.XboxIdentityProvider	9WZDNCRD1HKW	A, B, C
51.	Microsoft.XboxSpeechToTextOverlay	9P086NHDNB9W	A, B, C
52.	Microsoft.YourPhone	9NMPJ99VJBWV	A, B, C
53.	MicrosoftCorporationII.QuickAssist	9P7BP5VNWKX5	A, B, C
54.	MicrosoftWindows.Client.WebExperience	9MSSGKG348SP	A, B, C

5.3. InBox Apps:已安装

5.3.1. 查看

 $Get-AppXProvisionedPackage - Path "D: \OS_11_Custom \Install \Install \Mount" \mid Out-Grid View$

5.3.2. 导出到 Csv

\$SaveTo = "D:\OS_11_Custom\Install\Install\Report.\$(Get-Date -Format "yyyyMMddHHmmss").csv"

Get-AppXProvisionedPackage -Path "D:\OS_11_Custom\Install\Install\Mount" | Export-CSV -NoType -Path \$SaveTo

Write-host \$SaveTo -ForegroundColor Green

5.4. 删除已安装的所有预应用程序

- Install.InBox.Appx.Clear.all.ps1
 - o \Expand\Install\Install.InBox.Appx.Clear.all.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install/Install.InBox.Appx.Clea r.all.ps1

• 复制代码

Get-AppXProvisionedPackage -path "D:\OS_11_Custom\Install\Install\Mount" -ErrorAction SilentlyContinue | ForEach-Object {

Write-host "`n \$(\$_.DisplayName)"

Write-Host " Deleting ".PadRight(22) -NoNewline

try {

 $Remove-AppxProvisioned Package - Path "D: \OS_11_Custom \Install \Install \Mount" - Package \Name \\ + _. Package \Name \\ - Error Action \\ Silently Continue \\ | Out-Null \\$

Write-host "Finish" -ForegroundColor Green

} catch {

Write-host "Failed" -ForegroundColor Red

区域标记: 了解 5.5.

了解区域标记前,先了解 ZuneMusic 应用程序可用的语言列表: en-us, en-gb, as-in, az-latn-az, bs-latn-ba, bn-in, cs-cz, cy-gb, arsa, de-de, af-za, am-et, da-dk, el-gr, es-es, es-mx, ca-es, ca-es-valencia, eu-es, fi-fi, bg-bg, ga-ie, et-ee, gl-es, gu-in, gd-gb, fil-ph, fr-ca, frfr, hy-am, fa-ir, hu-hu, id-id, it-it, ja-jp, hr-hr, ka-ge, is-is, he-il, hi-in, kk-kz, lo-la, km-kh, lt-lt, kn-in, kok-in, ko-kr, mk-mk, lv-lv, ms-my, minz, mr-in, mt-mt, ne-np, nl-nl, nb-no, ml-in, nn-no, lb-lu, or-in, ro-ro, sk-sk, ru-ru, pl-pl, quz-pe, pt-br, pt-pt, sq-al, ta-in, th-th, sv-se, pa-in, sr-cyrl-ba, sr-cyrl-rs, sr-latn-rs, ur-pk, ug-cn, tr-tr, uk-ua, tt-ru, zh-cn, vi-vn, uz-latn-uz, sl-si, zh-tw, te-in

查看脱机映像已安装的语言

Dism /Image:"D:\OS_11_Custom\Install\Install\Mount" /Get-Intl

查看结果已安装的语言: en-US、zh-CN,在安装 ZuneMusic 应用时,安装程序会匹配"已安装的语言",自动过滤未安装的语 言列表,这就是区域标记。

区域标记:添加方式 5.6.

> 5.6.1. 执行"语言包:添加"

安装"本地语言体验包 (LXPs)" 5.6.2.

微软官方向 Windows 10 提供了本地语言体验包 (LXPS) 安装文件, Windows 11 不再提供, 想获取:

使用"Windows 本地语言体验包 (LXPs) 下载器"下载 5.6.2.1.

了解: https://github.com/ilikeyi/LXPs

下载后保存到: D:\OS_11_Custom\Install\InBox.Appx, 文件格式: LanguageExperiencePack.zh-

CN.Neutral.Appx

手动下载 5.6.2.2.

5.6.2.2.1. 区域

区域	产品ID	区域	产品ID
en-US	C9PDSCC711RVF	af-za	9PDW16B5HMXR
am-et	9NGL4R61W3PL	ar-sa	9N4S78P86PKX
as-in	9NTJLXMXX35J	az-latn-az	9P5TFKZHQ5K8
be-by	9MXPBGNNDW3L	bg-bg	9MX54588434F
bn-bd	9PH7TKVXGGM8	bn-in	9P1M44L7W84T

bs-latn-ba	9MVFKLJ10MFL	ca-es	9P6JMKJQZ9S7
ca-es-valencia	9P9K3WMFSW90	chr-cher-us	9MX15485N3RK
CS-CZ	9P3WXZ1KTM7C	cy-gb	9NKJ9TBML4HB
da-dk	9NDMT2VKSNL1	de-de	9P6CT0SLW589
el-gr	9N586B13PBLD	en-gb	9NT52VQ39BVN
es-es	9NWVGWLHPB1Z	es-mx	9N8MCM1X3928
et-ee	9NFBHFMCR30L	eu-es	9NMCHQHZ37HZ
fa-ir	9NGS7DD4QS21	fi-fi	9MW3PQ7SD3QK
fil-ph	9NWM2KGTDSSS	fr-ca	9MTP2VP0VL92
fr-fr	9NHMG4BJKMDG	ga-ie	9P0L5Q848KXT
gd-gb	9P1DBPF36BF3	gl-es	9NXRNBRNJN9B
gu-in	9P2HMSWDJDQ1	ha-latn-ng	9N1L95DBGRG3
he-il	9NB6ZFND5HCQ	hi-in	9NZC3GRX8LD3
hr-hr	9NW01VND4LTW	hu-hu	9MWN3C58HL87
hy-am	9NKM28TM6P67	id-id	9P4X3N4SDK8P
ig-ng	9PG4ZFJ48JSX	is-is	9NTHJR7TQXX1
it-it	9P8PQWNS6VJX	ja-jp	9N1W692FV4S1
ka-ge	9P60JZL05WGH	kk-kz	9PHV179R97LV
km-kh	9PGKTS4JS531	kn-in	9NC6DB7N95F9
kok-in	9MV3P55CMZ6P	ko-kr	9N4TXPCVRNGF
ku-arab-iq	9P1C18QL3D7H	ky-kg	9P7D3JJGZM48
lb-lu	9N0ST1WBZ9D9	lo-la	9N8X352G5NZV
lt-lt	9NWWD891H6HN	lv-lv	9N5CQDPH6SQT
mi-nz	9P2GDFB3JPSX	mk-mk	9P1X6XB1K3RN
ml-in	9NWDTV8FFV7L	mn-mn	9PG1DHC4VTZW
mr-in	9MWXCKHJVR1J	ms-my	9NPXL8ZSDDQ7
mt-mt	9PDG96SQ6BN8	nb-no	9N6J0M5DHCK0
ne-np	9P7CHPLWDQVN	nl-nl	9PF1C9NB5PRV
nn-no	9PK7KM3Z06KH	nso-za	9NS49QLX5CDV
or-in	9NTHCXCXSJDH	pa-arab-pk	9NJRL03WH6FM
pa-in	9NSNC0ZJX69B	pl-pl	9NC5HW94R0LD
prs-af	9P3NGC6X5ZQC	pt-br	9P8LBDM4FW35
pt-pt	9P7X8QJ7FL0X	quc-latn-gt	9P2V6MNNQZ0B
quz-pe	9NHTX8NVQ04K	ro-ro	9MWXGPJ5PJ3H

ru-ru	9NMJCX77QKPX	rw-rw	9NFW0M20H9WG
sd-arab-pk	9NB9JSCXW9X5	si-lk	9NVF9QSLGTL0
sk-sk	9N7LSNN099WB	sl-si	9NV27L34J4ST
sq-al	9MWLRGNMDGK7	sr-cyrl-ba	9MXGN7V65C7B
sr-cyrl-rs	9PPD6CCK9K5H	sr-latn-rs	9NBZ0SJDPPVT
sv-se	9P0HSNX08177	sw-ke	9NFF2M19DQ55
ta-in	9PDZB1WT1B34	te-in	9PMQJJGF63FW
tg-cyrl-tj	9MZHLBPPT2HC	th-th	9MSTWFRL0LR4
ti-et	9NC8C9RDNK2S	tk-tm	9NKHQ4GL6VLT
tn-za	9NFSXM123DHT	tr-tr	9NL1D3T5HG9R
tt-ru	9NV90Q1X1ZR2	ug-cn	9P52C5D7VL5S
uk-ua	9PPPMZRSGHR8	ur-pk	9NDWFTFW12BQ
uz-latn-uz	9P5P2T5P5L9S	vi-vn	9P0W68X0XZPT
wo-sn	9NH3SW1CR90F	xh-za	9NW3QWSLQD17
yo-ng	9NGM3VPPZS5V	zh-cn	9NRMNT6GMZ7
zh-tw	9PCJ4DHCQ1JQ	zu-za	9NNRM7KT5NB0

下载区域: zh-CN,应用程序ID: 9NRMNT6GMZ70,商店连接:

https://www.microsoft.com/store/productId/9NRMNT6GMZ70

5.6.2.2.2. 打开网站: https://store.rg-adguard.net

5.6.2.2.2.1. 搜索关键词:

https://www.microsoft.com/store/productId/9NRMNT6GMZ70

5.6.2.2.2.2. 网页内搜索 22621 内容, 搜索结果:

 ${\bf Microsoft.} Language {\bf Experience Packzh-CN_22621.*.}$

neutral__8wekyb3d8bbwe.appx

5.6.2.2.2.3. 下载后保存到 D:\OS_11_Custom\Install\Install\Install\InBox.Appx 目录里, 重命

名: LanguageExperiencePack.zh-cn.Neutral.Appx

5.6.2.3. 执行安装命令安装本地语言体验包 (LXPs)

了解区域标记添加方式后,获得 Language Experience Pack.zh-cn. Neutral 后,执行安装命令:

 $\label{lem:linstall_mount} Add-AppxProvisionedPackage - Path "D:\OS_11_Custom\Install\Instal$

5.6.2.4. InBox Apps: 已安装的应用程序包



5.6.2.4.1. 查看

5.6.2.4.2. 导到出 Csv

 $\label{lem:saweto} $$saveTo = "D:\OS_11_Custom\Install\Install\Report.$(Get-Date\-Format\"yyyyMMddHHmmss").csv"$

 $\label{lem:condition} Get-AppXProvisionedPackage - Path "D:\OS_11_Custom\Install\Install\Mount" \mid Export-CSV-NoType - Path $SaveTo$

Write-host \$SaveTo -ForegroundColor Green

5.7. InBox Apps:安装

5.7.1. 挂载或解压 InBox Apps 安装文件

挂载 22621.1.220506-1250.ni_release_amd64fre_InboxApps.iso 或解压到任意位置;

5.7.2. 执行安装命令后安装 InBox Apps 到: Install.wim

- Auto = 自动搜索本地所有磁盘, 默认;
- 自定义路径,例如指定为 F 盘: \$ISO = "F:\packages"
- 架构: x64
- Install.Inst.InBox.Appx.ps1
 - o \Expand\Install\Install.Inst.InBox.Appx.ps1
 - https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install.Inst
 .InBox.Appx.ps1

• 复制代码

```
$ISO = "Auto"

$Mount = "D:\OS_11_Custom\Install\Install\Mount"

$Arch = "x64"
```

Write-host "`n Offline image version: " -NoNewline

\$Current_Edition_Version = (Get-WindowsEdition -Path \$Mount).Edition

 $Write-Host \\ \$ Current_Edition_Version \\ -Foreground \\ Color \\ Green$

} catch {

try {

Write-Host "Error" -ForegroundColor Red



```
Write-Host " $($_)" -ForegroundColor Yellow
 return
$Pre_Config_Rules = @{
 Edition = @(
   @{
     Name = @( "CloudEdition"; )
     Apps = @(
       "Microsoft.UI.Xaml.2.3"; "Microsoft.UI.Xaml.2.4"; "Microsoft.UI.Xaml.2.7"; "Microsoft.UI.Xaml.2.8";
"Microsoft.NET.Native.Framework.2.2"; "Microsoft.NET.Native.Runtime.2.2"; "Microsoft.VCLibs.140.00";
"Microsoft.VCLibs.140.00.UWPDesktop"; "Microsoft.Services.Store.Engagement"; "Microsoft.VP9VideoExtensions";
"Clipchamp.Clipchamp"; "Microsoft.BingNews"; "Microsoft.BingWeather"; "Microsoft.DesktopAppInstaller";
"Microsoft.GetHelp"; "Microsoft.Getstarted"; "Microsoft.HEIFImageExtension"; "Microsoft.HEVCVideoExtension";
"Microsoft.MicrosoftOfficeHub"; "Microsoft.MicrosoftStickyNotes"; "Microsoft.MinecraftEducationEdition";
"Microsoft.Paint"; "Microsoft.RawImageExtension"; "Microsoft.ScreenSketch"; "Microsoft.SecHealthUI";
"Microsoft.StorePurchaseApp"; "Microsoft.Todos"; "Microsoft.WebMediaExtensions"; "Microsoft.WebpImageExtension";
"Microsoft.Whiteboard"; "Microsoft.Windows.Photos"; "Microsoft.WindowsAlarms"; "Microsoft.WindowsCalculator";
"Microsoft.WindowsCamera"; "Microsoft.WindowsFeedbackHub"; "Microsoft.WindowsMaps";
"Microsoft.WindowsNotepad"; "Microsoft.WindowsSoundRecorder"; "Microsoft.Xbox.TCUI";
"Microsoft.XboxIdentityProvider"; "Microsoft.XboxSpeechToTextOverlay"; "Microsoft.ZuneMusic"; "Microsoft.ZuneVideo";
"MicrosoftCorporationII.QuickAssist";
   @{
     Name = @( "CloudEditionN"; )
     Apps = @(
       "Microsoft.UI.Xaml.2.3"; "Microsoft.UI.Xaml.2.4"; "Microsoft.UI.Xaml.2.7"; "Microsoft.UI.Xaml.2.8";
"Microsoft.NET.Native.Framework.2.2"; "Microsoft.NET.Native.Runtime.2.2"; "Microsoft.VCLibs.140.00";
"Microsoft.VCLibs.140.00.UWPDesktop"; "Microsoft.Services.Store.Engagement"; "Microsoft.XboxSpeechToTextOverlay";
"Clipchamp.Clipchamp"; "Microsoft.BingNews"; "Microsoft.BingWeather"; "Microsoft.DesktopAppInstaller";
"Microsoft.GetHelp"; "Microsoft.Getstarted"; "Microsoft.MicrosoftOfficeHub"; "Microsoft.MicrosoftStickyNotes";
"Microsoft.MinecraftEducationEdition"; "Microsoft.Paint"; "Microsoft.ScreenSketch"; "Microsoft.SecHealthUI";
"Microsoft.StorePurchaseApp"; "Microsoft.Whiteboard"; "Microsoft.Windows.Photos"; "Microsoft.WindowsAlarms";
"Microsoft.WindowsCalculator"; "Microsoft.WindowsCamera"; "Microsoft.WindowsFeedbackHub";
"Microsoft.WindowsMaps"; "Microsoft.WindowsNotepad"; "Microsoft.XboxIdentityProvider";
"MicrosoftCorporationII.QuickAssist";
   @{
     Name = @( "Core"; "CoreN"; "CoreSingleLanguage"; )
     Apps = @(
       "Microsoft.UI.Xaml.2.3"; "Microsoft.UI.Xaml.2.4"; "Microsoft.UI.Xaml.2.7"; "Microsoft.UI.Xaml.2.8";
```

"Microsoft.NET.Native.Framework.2.2"; "Microsoft.NET.Native.Runtime.2.2"; "Microsoft.VCLibs.140.00";

Yi's Solutions

```
"Microsoft.VCLibs.140.00.UWPDesktop"; "Microsoft.Services.Store.Engagement"; "Microsoft.HEIFImageExtension";
"Microsoft.HEVCVideoExtension"; "Microsoft.SecHealthUI"; "Microsoft.VP9VideoExtensions";
"Microsoft.WebpImageExtension"; "Microsoft.WindowsStore"; "Microsoft.GamingApp"; "Microsoft.MicrosoftStickyNotes";
"Microsoft.Paint"; "Microsoft.PowerAutomateDesktop"; "Microsoft.ScreenSketch"; "Microsoft.WindowsNotepad";
"Microsoft.WindowsTerminal"; "Clipchamp.Clipchamp"; "Microsoft.MicrosoftSolitaireCollection";
"Microsoft.WindowsAlarms"; "Microsoft.WindowsFeedbackHub"; "Microsoft.WindowsMaps"; "Microsoft.ZuneMusic";
"Microsoft.BingNews"; "Microsoft.BingWeather"; "Microsoft.DesktopAppInstaller"; "Microsoft.WindowsCamera";
"Microsoft.Getstarted"; "Microsoft.Cortana"; "Microsoft.GetHelp"; "Microsoft.MicrosoftOfficeHub"; "Microsoft.People";
"Microsoft.StorePurchaseApp"; "Microsoft.Todos"; "Microsoft.WebMediaExtensions"; "Microsoft.Windows.Photos";
"Microsoft.WindowsCalculator"; "Microsoft.windowscommunicationsapps"; "Microsoft.WindowsSoundRecorder";
"Microsoft.Xbox.TCUI"; "Microsoft.XboxGameOverlay"; "Microsoft.XboxGamingOverlay"; "Microsoft.XboxIdentityProvider";
"Microsoft.XboxSpeechToTextOverlay"; "Microsoft.YourPhone"; "Microsoft.ZuneVideo";
"MicrosoftCorporationII.QuickAssist"; "MicrosoftWindows.Client.WebExperience"; "Microsoft.RawImageExtension";
"MicrosoftCorporationII.MicrosoftFamily";
   @{
     Name = @( "Education"; "Professional"; "ProfessionalEducation"; "ProfessionalWorkstation"; "Enterprise";
"IoTEnterprise"; "ServerRdsh"; )
     Apps = @(
       "Microsoft.UI.Xaml.2.3"; "Microsoft.UI.Xaml.2.4"; "Microsoft.UI.Xaml.2.7"; "Microsoft.UI.Xaml.2.8";
"Microsoft.NET.Native.Framework.2.2"; "Microsoft.NET.Native.Runtime.2.2"; "Microsoft.VCLibs.140.00";
"Microsoft.VCLibs.140.00.UWPDesktop"; "Microsoft.Services.Store.Engagement"; "Microsoft.HEIFImageExtension";
"Microsoft.HEVCVideoExtension"; "Microsoft.SecHealthUI"; "Microsoft.VP9VideoExtensions";
"Microsoft.WebpImageExtension"; "Microsoft.WindowsStore"; "Microsoft.GamingApp"; "Microsoft.MicrosoftStickyNotes";
"Microsoft.Paint"; "Microsoft.PowerAutomateDesktop"; "Microsoft.ScreenSketch"; "Microsoft.WindowsNotepad";
"Microsoft.WindowsTerminal"; "Clipchamp.Clipchamp"; "Microsoft.MicrosoftSolitaireCollection";
"Microsoft.WindowsAlarms"; "Microsoft.WindowsFeedbackHub"; "Microsoft.WindowsMaps"; "Microsoft.ZuneMusic";
"Microsoft.BingNews"; "Microsoft.BingWeather"; "Microsoft.DesktopAppInstaller"; "Microsoft.WindowsCamera";
"Microsoft.Getstarted"; "Microsoft.Cortana"; "Microsoft.GetHelp"; "Microsoft.MicrosoftOfficeHub"; "Microsoft.People";
"Microsoft.StorePurchaseApp"; "Microsoft.Todos"; "Microsoft.WebMediaExtensions"; "Microsoft.Windows.Photos";
"Microsoft.WindowsCalculator"; "Microsoft.windowscommunicationsapps"; "Microsoft.WindowsSoundRecorder";
"Microsoft.Xbox.TCUI"; "Microsoft.XboxGameOverlay"; "Microsoft.XboxGamingOverlay"; "Microsoft.XboxIdentityProvider";
"Microsoft.XboxSpeechToTextOverlay"; "Microsoft.YourPhone"; "Microsoft.ZuneVideo";
"MicrosoftCorporationII.QuickAssist"; "MicrosoftWindows.Client.WebExperience"; "Microsoft.RawImageExtension";
   @{
     Name = @( "EnterpriseN"; "EnterpriseGN"; "EnterpriseSN"; "ProfessionalN"; "EducationN";
"ProfessionalWorkstationN"; "ProfessionalEducationN"; "CloudN"; "CloudEN"; "CloudEditionLN"; "StarterN")
     Apps = @(
       "Microsoft.UI.Xaml.2.3"; "Microsoft.UI.Xaml.2.4"; "Microsoft.UI.Xaml.2.7"; "Microsoft.UI.Xaml.2.8";
"Microsoft.NET.Native.Framework.2.2"; "Microsoft.NET.Native.Runtime.2.2"; "Microsoft.VCLibs.140.00";
"Microsoft.VCLibs.140.00.UWPDesktop"; "Microsoft.Services.Store.Engagement"; "Microsoft.SecHealthUI";
"Microsoft.WindowsStore"; "Microsoft.MicrosoftStickyNotes"; "Microsoft.Paint"; "Microsoft.PowerAutomateDesktop";
"Microsoft.ScreenSketch"; "Microsoft.WindowsNotepad"; "Microsoft.WindowsTerminal"; "Clipchamp.Clipchamp";
"Microsoft.MicrosoftSolitaireCollection"; "Microsoft.WindowsAlarms"; "Microsoft.WindowsFeedbackHub";
"Microsoft.WindowsMaps"; "Microsoft.BingNews"; "Microsoft.BingWeather"; "Microsoft.DesktopAppInstaller";
"Microsoft.WindowsCamera"; "Microsoft.Getstarted"; "Microsoft.Cortana"; "Microsoft.GetHelp";
```

```
"Microsoft.MicrosoftOfficeHub"; "Microsoft.People"; "Microsoft.StorePurchaseApp"; "Microsoft.Todos";
"Microsoft.Windows.Photos"; "Microsoft.WindowsCalculator"; "Microsoft.windowscommunicationsapps";
"Microsoft.XboxGameOverlay"; "Microsoft.XboxIdentityProvider"; "Microsoft.XboxSpeechToTextOverlay";
"Microsoft.YourPhone"; "MicrosoftCorporationII.QuickAssist"; "MicrosoftWindows.Client.WebExperience";
   Rule=@(
      @{ Name="Microsoft.UI.Xaml.2.3"; Match="UI.Xaml*{ARCHC}*2.3"; License="UI.Xaml*{ARCHC}*2.3";
Dependencies=@(); }
      @{ Name="Microsoft.UI.Xaml.2.4"; Match="UI.Xaml*{ARCHTag}*2.4"; License="UI.Xaml*{ARCHTag}*2.4";
Dependencies=@(); }
      @{ Name="Microsoft.UI.Xaml.2.7"; Match="UI.Xaml*{ARCHTag}*2.7"; License="UI.Xaml*{ARCHTag}*2.7";
Dependencies=@(); }
      @{ Name="Microsoft.UI.Xaml.2.8"; Match="UI.Xaml*{ARCHTag}*2.8"; License="UI.Xaml*{ARCHTag}*2.8";
Dependencies=@(); }
      @{ Name="Microsoft.NET.Native.Framework.2.2"; Match="Native.Framework*{ARCHTag}*2.2";
License="Native.Framework*{ARCHTag}*2.2"; Dependencies=@(); }
      @{ Name="Microsoft.NET.Native.Runtime.2.2"; Match="Native.Runtime*{ARCHTag}*2.2";
License="Native.Runtime*{ARCHTag}*2.2"; Dependencies=@(); }
      @{ Name="Microsoft.VCLibs.140.00"; Match="VCLibs*{ARCHTag}"; License="VCLibs*{ARCHTag}"; Dependencies=@(); }
      @{ Name="Microsoft.VCLibs.140.00.UWPDesktop"; Match="VCLibs*{ARCHTag}*Desktop";
License="VCLibs*{ARCHTag}*Desktop"; Dependencies=@(); }
      @{ Name="Microsoft.Services.Store.Engagement"; Match="Services.Store.Engagement*{ARCHC}";
License="Services.Store.Engagement*{ARCHC}"; Dependencies=@(); }
      @{ Name="Microsoft.HEIFImageExtension"; Match="HEIFImageExtension"; License="HEIFImageExtension*";
Dependencies=@("Microsoft.VCLibs.140.00"); }
      @{ Name="Microsoft.HEVCVideoExtension"; Match="HEVCVideoExtension*{ARCHC}";
License="HEVCVideoExtension*{ARCHC}*xml"; Dependencies=@("Microsoft.VCLibs.140.00"); }
      @{ Name="Microsoft.SecHealthUI"; Match="SecHealthUI*{ARCHC}"; License="SecHealthUI*{ARCHC}";
Dependencies=@("Microsoft.UI.Xaml.2.4","Microsoft.VCLibs.140.00"); }
      @{ Name="Microsoft.VP9VideoExtensions"; Match="VP9VideoExtensions*{ARCHC}";
License="VP9VideoExtensions*{ARCHC}"; Dependencies=@("Microsoft.VCLibs.140.00"); }
      @{ Name="Microsoft.WebpImageExtension"; Match="WebpImageExtension*{ARCHC}"; }
License="WebpImageExtension*{ARCHC}"; Dependencies=@("Microsoft.VCLibs.140.00"); }
      @{ Name="Microsoft.WindowsStore"; Match="WindowsStore"; License="WindowsStore";
Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00"); }
      @{ Name="Microsoft.GamingApp"; Match="GamingApp"; License="GamingApp";
Dependencies=@("Microsoft.UI.Xaml.2.3","Microsoft.VCLibs.140.00","Microsoft.VCLibs.140.00.UWPDesktop"); }
      @{ Name="Microsoft.MicrosoftStickyNotes"; Match="MicrosoftStickyNotes"; License="MicrosoftStickyNotes";
Dependencies=@("Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.VCLibs.140.00");}
```

```
@{ Name="Microsoft.Paint"; Match="Paint"; License="Paint";
 Dependencies=@("Microsoft.VCLibs.140.00","Microsoft.VCLibs.140.00.UWPDesktop","Microsoft.UI.Xaml.2.7"); }
                     @{ Name="Microsoft.PowerAutomateDesktop"; Match="PowerAutomateDesktop"; License="PowerAutomateDesktop";
Dependencies=@("Microsoft.VCLibs.140.00.UWPDesktop"); }
                     @{Name="Microsoft.ScreenSketch"; Match="ScreenSketch"; License="ScreenSketch";
Dependencies=@("Microsoft.UI.Xaml.2.7", "Microsoft.VCLibs.140.00"); }
                     @{ Name="Microsoft.WindowsNotepad"; Match="WindowsNotepad"; License="WindowsNotepad";
 Dependencies=@("Microsoft.VCLibs.140.00","Microsoft.VCLibs.140.00.UWPDesktop","Microsoft.UI.Xaml.2.7"); }
                     @{ Name="Microsoft.WindowsTerminal"; Match="WindowsTerminal"; License="WindowsTerminal";
Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.VCLibs.140.00.UWPDesktop"); }
                     @{ Name="Clipchamp.Clipchamp"; Match="Clipchamp.Clipchamp"; License="Clipchamp.Clipchamp";
Dependencies=@(); }
                     @{ Name="Microsoft.MicrosoftSolitaireCollection"; Match="MicrosoftSolitaireCollection";
License="MicrosoftSolitaireCollection";
 Dependencies=@("Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.VCLibs.140.00");}
                     @{ Name="Microsoft.WindowsAlarms"; Match="WindowsAlarms"; License="WindowsAlarms";
 Dependencies=@("Microsoft.UI.Xaml.2.8","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00","Microsoft.VCLibs.140.00.UWPDesktop"); }
                     @{ Name="Microsoft.WindowsFeedbackHub"; Match="WindowsFeedbackHub"; License="WindowsFeedbackHub";
Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00"); }
                     @{ Name="Microsoft.WindowsMaps"; Match="WindowsMaps"; License="WindowsMaps";
 Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
 osoft.VCLibs.140.00"); }
                     @{ Name="Microsoft.ZuneMusic"; Match="ZuneMusic"; License="ZuneMusic";
 Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00"); }
                     @{ Name="MicrosoftCorporationII.MicrosoftFamily"; Match="MicrosoftFamily"; License="MicrosoftFamily";
Dependencies=@("Microsoft.VCLibs.140.00.UWPDesktop"); }
                     @{ Name="Microsoft.BingNews"; Match="BingNews"; License="BingNews";
Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00"); }
                     @{ Name="Microsoft.BingWeather"; Match="BingWeather"; License="BingWeather";
 Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00"); }
                     @{ Name="Microsoft.DesktopAppInstaller"; Match="DesktopAppInstaller"; License="DesktopAppInstaller";
Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.VCLibs.140.00.UWPDesktop");}
                     @{ Name="Microsoft.WindowsCamera"; Match="WindowsCamera"; License="WindowsCamera";
Dependencies=@("Microsoft.UI.Xaml.2.8","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00"); }
                     @{ Name="Microsoft.Getstarted"; Match="Getstarted"; License="Getstarted";
 Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
 osoft.VCLibs.140.00"); }
                     @{ Name="Microsoft.Cortana"; Match="Cortana"; License="Cortana";
```

Dependencies=@("Microsoft.NET.Native.Framework.2.2", "Microsoft.NET.Native.Runtime.2.2", "Microsoft.VCLibs.140.00", "

```
@{ Name="Microsoft.GetHelp"; Match="GetHelp"; License="GetHelp";
Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00"); }
            @{ Name="Microsoft.MicrosoftOfficeHub"; Match="MicrosoftOfficeHub"; License="MicrosoftOfficeHub";
Dependencies=@("Microsoft.VCLibs.140.00","Microsoft.VCLibs.140.00.UWPDesktop"); }
            @{ Name="Microsoft.People"; Match="People"; License="People";
 Dependencies=@("Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.StorePurchaseApp"; Match="StorePurchaseApp"; License="StorePurchaseApp";
Dependencies=@("Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.Todos"; Match="Todos"; License="Todos";
Dependencies=@("Microsoft.UI.Xaml.2.8","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
 osoft.VCLibs.140.00", "Microsoft.VCLibs.140.00.UWPDesktop", "Microsoft.Services.Store.Engagement"); }
            @{ Name="Microsoft.WebMediaExtensions"; Match="WebMediaExtensions"; License="WebMediaExtensions";
 Dependencies=@("Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.Windows.Photos"; Match="Windows.Photos"; License="Windows.Photos";
 Dependencies=@("Microsoft.UI.Xaml.2.4", "Microsoft.NET.Native.Framework.2.2", "Microsoft.NET.Native.Runtime.2.2", "Microsoft.Net.Net.Native.Runtime.2.2", "Microsoft.Net.Net.N
osoft.VCLibs.140.00"); }
            @{ Name="Microsoft.WindowsCalculator"; Match="WindowsCalculator"; License="WindowsCalculator";
Dependencies=@("Microsoft.UI.Xaml.2.8","Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft.NET.Native.Runtime.2.2", Microsoft
osoft.VCLibs.140.00","Microsoft.VCLibs.140.00.UWPDesktop"); }
            @{ Name="Microsoft.windowscommunicationsapps"; Match="WindowsCommunicationsApps";
License="WindowsCommunicationsApps"; Dependencies=@("Microsoft.UI.Xaml.2.7","Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.WindowsSoundRecorder"; Match="WindowsSoundRecorder"; License="WindowsSoundRecorder";
Dependencies=@("Microsoft.UI.Xaml.2.3","Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.Xbox.TCUI"; Match="Xbox.TCUI"; License="Xbox.TCUI";
 Dependencies=@("Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.VCLibs.140.00");}
            @{ Name="Microsoft.XboxGameOverlay"; Match="XboxGameOverlay"; License="XboxGameOverlay";
Dependencies=@("Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.XboxGamingOverlay"; Match="XboxGamingOverlay"; License="XboxGamingOverlay";
Dependencies=@("Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.XboxIdentityProvider"; Match="XboxIdentityProvider"; License="XboxIdentityProvider";
Dependencies=@("Microsoft.NET.Native.Framework.2.2","Microsoft.NET.Native.Runtime.2.2","Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.XboxSpeechToTextOverlay"; Match="XboxSpeechToTextOverlay";
License="XboxSpeechToTextOverlay"; Dependencies=@("Microsoft.VCLibs.140.00"); }
            @{ Name="Microsoft.YourPhone"; Match="YourPhone"; License="YourPhone";
 Dependencies=@("Microsoft.VCLibs.140.00","Microsoft.VCLibs.140.00.UWPDesktop"); }
            @{ Name="Microsoft.ZuneVideo"; Match="ZuneVideo"; License="ZuneVideo";
 Dependencies=@("Microsoft.UI.Xaml.2.7", "Microsoft.VCLibs.140.00"); }
            @{ Name="MicrosoftCorporationII.QuickAssist"; Match="QuickAssist"; License="QuickAssist";
 Dependencies=@("Microsoft.VCLibs.140.00.UWPDesktop"); }
            @{ Name="MicrosoftWindows.Client.WebExperience"; Match="WebExperience"; License="WebExperience";
 Dependencies=@("Microsoft.VCLibs.140.00"); }
```

Microsoft.VCLibs.140.00.UWPDesktop"); }

```
@{ Name="Microsoft.MinecraftEducationEdition"; Match="MinecraftEducationEdition";
License="MinecraftEducationEdition"; Dependencies=@("Microsoft.VCLibs.140.00.UWPDesktop"); }
             @{ Name="Microsoft.Whiteboard"; Match="Whiteboard"; License="Whiteboard";
 Dependencies = @("Microsoft.NET.Native.Framework.2.2", "Microsoft.NET.Native.Runtime.2.2", "Microsoft.VCLibs.140.00"); \} \\
             @\{ Name="Microsoft.RawlmageExtension"; License="RawlmageExtension"; Lice
Dependencies=@(); }
 $Allow_Install_App = @()
 ForEach ($item in $Pre_Config_Rules.Edition) {
       if ($item.Name -contains $Current_Edition_Version) {
             Write-host "`n Match to: "-NoNewline; Write-host $Current_Edition_Version -ForegroundColor Green
             $Allow_Install_App = $item.Apps
             break
Write-host "`n The app to install ( $($Allow_Install_App.Count) item )" -ForegroundColor Yellow
Write-host " $('-' * 80)"
ForEach ($item in $Allow_Install_App) {
       Write-host " $($item)" -ForegroundColor Green
Function Match_InBox_Apps_Install_Pack
       param ( $NewPath )
       $NewArch = $Arch
       $NewArchC = $Arch.Replace("AMD64", "x64")
       $NewArchCTag = $Arch.Replace("AMD64", "x64")
       if ($Arch -eq "arm64") { $NewArchCTag = "arm" }
       if ($Pre_Config_Rules.Rule.Count -gt 0) {
              ForEach ($itemInBoxApps in $Pre_Config_Rules.Rule){
                   $InstallPacker = ""
                   $InstallPackerCert = ""
                    \ensuremath{\$}SearchNewStructure = \ensuremath{\$}itemInBoxApps.Match.Replace("{ARCH}", \ensuremath{\$}NewArch).Replace("{ARCHC}", \ensuremath{\$}Ne
 $NewArchC).Replace("{ARCHTag}", $NewArchCTag)
                    $SearchNewLicense = $itemInBoxApps.License.Replace("{ARCH}", $NewArch).Replace("{ARCHC}",
 $NewArchC).Replace("{ARCHTag}", $NewArchCTag)
```

```
Get-ChildItem -Path $NewPath -Filter "*$($SearchNewStructure)*" -Include "*.appx", "*.appxbundle", "*.msixbundle"
-Recurse -Force -ErrorAction SilentlyContinue | ForEach-Object {
       if (Test-Path -Path $_.FullName -PathType Leaf) {
         $InstallPacker = $_.FullName
         Get-ChildItem -Path $NewPath -Filter "*$($SearchNewLicense)*" -Include *.xml -Recurse -Force -ErrorAction
SilentlyContinue | ForEach-Object {
          $InstallPackerCert = $_.FullName
         $Script:InBoxAppx += @{
          Name = $itemInBoxApps.Name;
           Depend = $itemInBoxApps.Dependencies;
           Search = $SearchNewStructure;
          InstallPacker = $InstallPacker;
           Certificate = $InstallPackerCert
           CertificateRule = $SearchNewLicense
         return
Write-host "`n InBox Apps: Installation packages, automatic search for full disk or specified paths" -ForegroundColor
Yellow
Write-host " $('-' * 80)"
$Script:InBoxAppx = @()
if ($ISO -eq "Auto") {
  Get-PSDrive -PSProvider FileSystem -ErrorAction SilentlyContinue | ForEach-Object {
   $AppPath = Join-Path -Path $_.Root -ChildPath "packages" -ErrorAction SilentlyContinue
   Match_InBox_Apps_Install_Pack -NewPath $AppPath
} else {
 Match_InBox_Apps_Install_Pack -NewPath $ISO
Write-host "Search Complete" -ForegroundColor Green
Write-host "`n InBox Apps: Installer Match Results" -ForegroundColor Yellow
```

```
Write-host " $('-' * 80)"
if ($Script:InBoxAppx.Count -gt 0) {
  Write-host " Match successful" -ForegroundColor Green
} else {
  Write-host "Failed match" -ForegroundColor Red
  return
Write-host "`n InBox Apps: Details of the application to be installed ( $($Script:InBoxAppx.Count) item )" -ForegroundColor
Write-host " $('-' * 80)"
ForEach ($Rule in $Script:InBoxAppx) {
  Write-host " Apps name: " -NoNewline; Write-host $Rule.Name -ForegroundColor Yellow
  Write-host " Apps installer: " -NoNewline; Write-host $Rule.InstallPacker -ForegroundColor Yellow
  Write-host " License: "-NoNewline; Write-host $Rule.Certificate -ForegroundColor Yellow
  Write-host ""
Write-host "`n InBox Apps: Installation" -ForegroundColor Yellow
Write-host " $('-' * 80)"
ForEach ($Rule in $Script:InBoxAppx) {
  Write-host " Name: " -NoNewline; Write-host $Rule.Name -ForegroundColor Yellow
  Write-host " $('-' * 80)"
  if($Allow_Install_App -contains $Rule.Name) {
    Write-host "Search for apps: "-NoNewline; Write-host $Rule.InstallPacker -ForegroundColor Yellow
    Write-host "Search for License: "-NoNewline; Write-host $Rule.Certificate -ForegroundColor Yellow
    if (Test-Path -Path $Rule.InstallPacker -PathType Leaf) {
     if (Test-Path -Path $Rule.Certificate -PathType Leaf) {
       Write-host "License: "-NoNewline
       Write-host $Rule.Certificate -ForegroundColor Yellow
       Write-host " With License".PadRight(22) -NoNewline -ForegroundColor Green
       Write-host " Installing".PadRight(22) -NoNewline
       try {
         Add-AppxProvisionedPackage -Path $Mount -PackagePath $Rule.InstallPacker -LicensePath $Rule.Certificate -
ErrorAction SilentlyContinue | Out-Null
         Write-Host "Done`n" -ForegroundColor Green
       } catch {
```

```
Write-Host "Failed" -ForegroundColor Red
        Write-Host " $($_)`n"-ForegroundColor Red
     } else {
       Write-host " No License".PadRight(22) -NoNewline -ForegroundColor Red
       Write-host " Installing".PadRight(22) -NoNewline
       try {
         Add-AppxProvisionedPackage -Path $Mount -PackagePath $Rule.InstallPacker -SkipLicense -ErrorAction
SilentlyContinue | Out-Null
         Write-Host "Done`n" -ForegroundColor Green
       } catch {
        Write-Host "Failed" -ForegroundColor Red
        Write-Host " $($_)`n"-ForegroundColor Red
   } else {
     Write-host " The installation package does not exist" -ForegroundColor Red
   }
 } else {
   Write-host "Skip the installation`n" -ForegroundColor Red
```

5.8. 区域标记:删除

- 完成安装 InBox Apps 应用后,区域标记已不再重要,可删除或不删除,删除"本地语言体验包(LXPs),简体中文-中国)",区域标记: zh-CN,可更改为其它区域标记。
- Install.Clear.Flag.ps1
 - o \Expand\Install\Install.Clear.Flag.ps1
 - $o \qquad https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install.Clear.Flag.ps1 \\$

• 复制代码

```
$Lang = "zh-CN"

Get-AppXProvisionedPackage -Path "D:\OS_11_Custom\Install\Install\Mount" | Foreach-object {

if ($_.DisplayName -Like "*LanguageExperiencePack*$($Lang)*") {

Write-host " $($_.DisplayName)"
```

```
Write-Host " Deleting ".PadRight(22) -NoNewline

try {

Remove-AppxProvisionedPackage -Path "D:\OS_11_Custom\Install\Install\Mount" -PackageName $_.PackageName -ErrorAction

SilentlyContinue | Out-Null

Write-host "Finish" -ForegroundColor Green

} catch {

Write-host "Failed" -ForegroundColor Red

}
```

5.9. InBox Apps: 优化

在安装应用后,应优化预配 Appx 包,通过用硬链接替换相同的文件来减少应用的磁盘使用量,仅针对脱机映像。

 $\label{lem:limited} \begin{tabular}{ll} Dism/Image: "D:\OS_11_Custom\Install\Mount"/Optimize-Provisioned AppxPackages \\ \end{tabular}$

6. 累积更新

- 不同版本、旧版本升级到最新版时,需优先添加"功能启用包"后才能添加最新版累积更新;
- 添加语言包后,可安装与初始版本相同的累积更新,以解决安装后未刷新"组件:映像中已安装的所有包"状态的已知问题;
- 为保持最新,推荐您下载最新版。

6.1. 专属功能启用包

- o 学习: KB5027397: 使用启用包对 Windows 11 版本 23H2 的功能更新
- 制作 Windows 11 版本 22H2、23H2 时,需提前安装"功能启用包"后才能安装 22631.* 的累积更新,下载后保存到: D:\OS_11_Custom\Install\Install\Update,根据架构选择下载:

6.1.1. x64, 默认

• 直连下载

 $https://catalog.sf.dl.delivery.mp.microsoft.com/filestreamingservice/files/caa3ff4a-6420-4341-aeae-33b2d7f463be/public/windows11.0-kb5027397-x64_3a9c368e239bb928c32a790cf1663338d2cad472.msu$

■ 添加

 $$KBPath = "D:\OS_11_Custom\Install\Update\windows11.0-kb5027397-x64_3a9c368e239bb928c32a790cf1663338d2cad472.msu"$

 ${\tt Add-WindowsPackage-Path~"D:\OS_11_Custom\Install\Install\Mount"-PackagePath~\$KBPath)}$



6.1.2. Arm64

直连下载

https://catalog.sf.dl.delivery.mp.microsoft.com/filestreamingservice/files/c29dd4ea-7f6a-4636-a991-29ba8ae70658/public/windows11.0-kb5027397-arm64_bacb74fba9077a5b7ae2f74a3ebb0b506f9708f3.msu

• 添加

 $\label{local-condition} $KBPath = "D:\OS_11_Custom\Install\Update\windows11.0-kb5027397-arm64_bacb74fba9077a5b7ae2f74a3ebb0b506f9708f3.msu"$

Add-WindowsPackage -Path "D:\OS_11_Custom\Install\Install\Mount" -PackagePath \$KBPath

6.2. 初始版本

- 微软官方已提供了 Windows 11 23H2 22631.2428 初始版本专属功能启用包,文件名: X23-59425_Windows11-23H2-FeatureEnablement.zip,压缩包里包含了以下文件: KB5031354、KB5027397。
- 优先添加"专属功能启用包"后再添加"初始版本",前往下载页面:

https://www.catalog.update.microsoft.com/Search.aspx?q=KB5031354, 下载后保存到:

D:\OS_11_Custom\Install\Install\Update,或通过直连下载,根据架构选择下载:

6.2.1. x64, 默认

• 直连下载

https://catalog.sf.dl.delivery.mp.microsoft.com/filestreamingservice/files/885dcacb-fb29-4536-88f6-4fd4792a4a65/public/windows11.0-kb5031354-x64_3391407e62562e0e48a437c5c7115667305d788c.msu

添加

 $BPath = D:OS_{11}Custom\lnstall\lnstall\Update\windows11.0-kb5031354-x64_3391407e62562e0e48a437c5c7115667305d788c.msu$

 $Add-Windows Package - Path "D: \OS_11_Custom \Install \Mount" - Package Path $KBPath \Add-Windows \Add-Wind$

6.2.2. Arm64

直连下载

 $https://catalog.sf.dl.delivery.mp.microsoft.com/filestreamingservice/files/e3e1d074-cfde-4c2d-ba0c-f6887db3b166/public/windows11.0-kb5031354-arm64_3848ce9f925f15d07ad1dd06fe976e6719634653.msu$

• 添加

 $$KBPath = "D:\OS_11_Custom\Install\Install\Update\windows11.0-kb5031354-arm64_3848ce9f925f15d07ad1dd06fe976e6719634653.msu"$

 $Add-Windows Package - Path "D: \OS_11_Custom \Install \Mount" - Package Path $KBPath \Add-Windows \Add-Wind$



6.3. 其它版本

- 安装前,下载专属功能启用包 KB5027397 后并优先后添加,再依次添加其它版本。
- 查阅"Windows 11 版本信息",例如下载累积更新: KB5035853,版本号: 22631.3296,前往下载页面: https://www.catalog.update.microsoft.com/Search.aspx?q=KB5035853,下载后保存到:
 D:\OS_11_Custom\Install\Update,或通过直连下载,根据架构选择下载:

6.3.1. x64, 默认

• 直连下载

https://catalog.sf.dl.delivery.mp.microsoft.com/filestreamingservice/files/594b22d5-84c3-4665-bdc7-3167c91759b9/public/windows11.0-kb5035853-x64_8ca1a9a646dbe25c071a8057f249633a61929efa.msu

添加

```
$KBPath = "D:\OS_11_Custom\Install\Install\Update\windows11.0-kb5035853-
x64_8ca1a9a646dbe25c071a8057f249633a61929efa.msu"
```

Add-WindowsPackage -Path "D:\OS_11_Custom\Install\Install\Mount" -PackagePath \$KBPath

6.3.2. Arm64

• 直连下载

https://catalog.sf.dl.delivery.mp.microsoft.com/filestreamingservice/files/72ba502a-7982-471c-aad2-355efddbff61/public/windows11.0-kb5035853-arm64_076c009bca80cfa85272bd50d65951c2f663fcc5.msu

• 添加

```
$KBPath = "D:\OS_11_Custom\Install\Install\Update\windows11.0-kb5035853-
arm64_076c009bca80cfa85272bd50d65951c2f663fcc5.msu"

Add-WindowsPackage -Path "D:\OS_11_Custom\Install\Install\Mount" -PackagePath $KBPath
```

6.4. 固化更新

固化后不可卸载,固化时将清理恢复映像并重置任何被取代的组件的基础。

 $\label{lem:limit} \begin{tabular}{ll} Dism/Image: "D: \OS_11_Custom \Install \Mount"/cleanup-image/StartComponentCleanup/ResetBase \end{tabular} \begin{tabular}{ll} According to the limit of the lim$

6.4.1. 固化更新后清理组件

```
$Mount = "D:\OS_11_Custom\Install\Install\Mount"

Get-WindowsPackage -Path $Mount -ErrorAction SilentlyContinue | ForEach-Object {

if ($_.PackageState -eq "Superseded") {

Write-Host " $($_.PackageName)" -ForegroundColor Green
```



}

ι

- 7. 驱动
- 8. 部署引擎:添加
 - 了解"部署引擎",如果添加到 ISO 安装介质,可跳过添加到已挂载;
 - 如果添加部署引擎到已挂载里,请继续在当前位置执行下一步。
- 9. 健康

保存前应检查是否损坏,健康状态异常时,中止保存

 $Repair-Windows Image - Path "D: \OS_11_Custom \Install \Install \Mount" - Scan Health \Install \Additional \Addi$

10. 替换 WinRE.wim

已批量替换 Install.wim 里的所有索引号里的 WinRE.wim 请跳过该步骤。

 $$WinRE = "D:\OS_11_Custom\Install\Install\Update\Winlib\WinRE.wim"$

 $\label{lem:copyTo} $$\operatorname{CopyTo} = "D:\OS_11_Custom\Install\Mount\Windows\System32\Recovery"$$$

Copy-Item -Path \$WinRE -Destination \$CopyTo -Force

11. 保存映像: Install.wim

Save-WindowsImage -Path "D:\OS_11_Custom\Install\Install\Mount"

12. 卸载映像: Install.wim

关闭所有可能正在访问映像中文件的应用程序,包括文件资源管理器。

 $\label{lem:linear_lin$

循环操作区域,结束。

- 13. 如何批量替换 Install.wim 里的所有索引号里的 WinRE.wim
 - 13.1. 获取 WimLib

前往 https://wimlib.net 官方网站后,选择不同的版本:arm64, x64, x86, 下载完成后解压到:D:\Wimlib



13.2.1. 从 Install.wim 里提取 WinRE.wim 文件 Install.wim

- Install.WinRE.Replace.wim.ps1
 - \Expand\Install\Install.WinRE.Replace.wim.ps1
 - https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install/Install.Win
 RE.Replace.wim.ps1

• 复制代码

```
$Arguments = @(

"extract",

"D:\OS_11\sources\install.wim", "1",

"\Windows\System32\Recovery\Winre.wim",

"--dest-dir=""D:\OS_11_Custom\Install\Install\Update\Winlib"""

)

New-Item -Path "D:\OS_11_Custom\Install\Install\Update\Winlib" -ItemType Directory -ea SilentlyContinue

Start-Process -FilePath "d:\wimlib\wimlib-imagex.exe" -ArgumentList $Arguments -wait -nonewwindow
```

13.2.2. 获取 Install.wim 所有索引号后并替换旧的 WinRE.wim

- Install.WinRE.Replace.wim.ps1
 - \Expand\Install\Install.WinRE.Replace.wim.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install.Win RE.Replace.wim.ps1

• 复制代码

```
Get-WindowsImage -ImagePath "D:\OS_11\sources\install.wim" -ErrorAction SilentlyContinue | ForEach-Object {

Write-Host " Image name: " -NoNewline; Write-Host $_.ImageName -ForegroundColor Yellow

Write-Host " The index number: " -NoNewline; Write-Host $_.ImageIndex -ForegroundColor Yellow

Write-Host "`n Replacement "

$Arguments = @(

"update",

"D:\OS_11\sources\install.wim", $_.ImageIndex,

"--command=""add 'D:\OS_11_Custom\Install\Install\Update\Winlib\WinRE.wim'

'\Windows\System32\Recovery\WinRe.wim'"""

)
```



}

14. 重建 Install.wim 后可缩小文件大小

- Install.Rebuild.wim.ps1
 - o \Expand\Install\Install.Rebuild.wim.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Install/Install.Rebuild.wim.ps1

复制代码

```
$InstallWim = "D:\OS_11\sources\install.wim"
Get-WindowsImage - ImagePath $InstallWim - ErrorAction SilentlyContinue | ForEach-Object {
 Write-Host " Image name: " -NoNewline
 Write-Host $_.ImageName -ForegroundColor Yellow
 Write-Host " The index number: " -NoNewline
 Write-Host $_.ImageIndex -ForegroundColor Yellow
 Write-Host "`n Under reconstruction".PadRight(28) -NoNewline
 Export-WindowsImage - SourceImagePath $InstallWim - SourceIndex $_.ImageIndex - DestinationImagePath "$($InstallWim).New" -
CompressionType max | Out-Null
 Write-Host "Finish`n" -ForegroundColor Green
if (Test-Path "$($InstallWim).New" -PathType Leaf) {
 Remove-Item -Path $InstallWim
 Move-Item -Path "$($InstallWim).New" -Destination $InstallWim
 Write-Host "Finish" -ForegroundColor Green
} else {
 Write-host "Failed" -ForegroundColor Red
```

II 自定义封装: boot.wim

1. 查看 Boot.wim 文件信息

映像名称、映像描述、映像大小、架构、版本、索引号等;

```
$ViewFile = "D:\OS_11\Sources\Boot.wim"
```

 $Get-Windows Image-ImagePath\ \$ViewFile\ |\ For each-Object\ \{\ Get-Windows Image-ImagePath\ \$ViewFile\ - index\ \$_. ImageIndex\ \}$

2. 指定挂载 Boot.wim 路径

New-Item -Path "D:\OS_11_Custom\Boot\Boot\Mount" -ItemType directory -ea SilentlyContinue

3. 开始挂载 Boot.wim

默认索引号: 2

Mount-WindowsImage -ImagePath "D:\OS_11\sources\boot.wim" -Index "2" -Path "D:\OS_11_Custom\Boot\Boot\Mount"

4. 语言包

- 自动安装语言包:获取"组件:映像中已安装的所有包"后进行匹配,匹配到对应的名称后,再安装本地对应的语言包文件,查看报告"语言安装包适用于 Boot.wim"。
- 添加语言时,须对应不同的架构版本,未对应时,添加过程中报错等提示。

4.1. 语言包:添加

- Boot.Instl.lang.ps1
 - \Expand\Boot\Boot.Instl.lang.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Boot/Boot.Instl.lang.ps1

• 复制代码

```
$Mount = "D:\OS_11_Custom\Boot\Boot\Boot\Language\Add\zh-CN"

$InitL_instalL_Language_Component = @()

Get-WindowsPackage -Path $Mount | ForEach-Object {
    $InitL_instalL_Language_Component += $_.PackageName
}

Add-WindowsPackage -Path $Mount -PackagePath "$($Sources)\WinPE-FontSupport-zh-CN.cab"

$Language_List = @(
    @{ Match = "*WinPE*Setup*Client*Package*"; File = "WINPE-SETUP-CLIENT_zh-CN.CAB"; }

    @{ Match = "*WinPE*Setup*Package*"; File = "WinPE-Setup_zh-CN.cab"; }

    @{ Match = "*WinPE-LanguagePack-Package*"; File = "lp.cab"; }

    @{ Match = "*SecureStartup*"; File = "winpe-securestartup_zh-CN.cab"; }

    @{ Match = "*ATBroker*"; File = "winpe-atbroker_zh-CN.cab"; }

    @{ Match = "*AudioCore*"; File = "winpe-audiocore_zh-CN.cab"; }

@{ Match = "*AudioDrivers*"; File = "winpe-audiodrivers_zh-CN.cab"; }

@{ Match = "*AudioDrivers*"; File = "winpe-audiodrivers_zh-CN.cab"; }
```

```
@{ Match = "*EnhancedStorage*"; File = "winpe-enhancedstorage_zh-CN.cab"; }
  @{ Match = "*Narrator*"; File = "winpe-narrator_zh-CN.cab"; }
 @{ Match = "*scripting*"; File = "winpe-scripting_zh-CN.cab"; }
  @{ Match = "*Speech-TTS*"; File = "winpe-speech-tts_zh-CN.cab"; }
 @{ Match = "*srh*"; File = "winpe-srh_zh-CN.cab"; }
  @{ Match = "*srt*"; File = "winpe-srt_zh-CN.cab"; }
  @{ Match = "*wds-tools*"; File = "winpe-wds-tools_zh-CN.cab"; }
  @{ Match = "*-WMI-Package*"; File = "winpe-wmi_zh-CN.cab"; }
ForEach ($Rule in $Language_List) {
 Write-host "`n Rule name: $($Rule.Match)" -ForegroundColor Yellow; Write-host "$('-' * 80)"
 ForEach ($Component in $Initl_install_Language_Component) {
   if ($Component -like "*$($Rule.Match)*") {
     Write-host " Component name: " -NoNewline; Write-host $Component -ForegroundColor Green
     Write-host " Language pack file: " -NoNewline; Write-host "$($Sources)\$($Rule.File)" -ForegroundColor Green
     Write-Host " Installing ".PadRight(22) -NoNewline
     try {
       Add-WindowsPackage -Path $Mount -PackagePath "$($Sources)\$($Rule.File)" | Out-Null
       Write-host "Finish" -ForegroundColor Green
     } catch {
       Write-host "Failed" -ForegroundColor Red
     break
```

4.2. 脱机映像语言: 更改

4.2.1. 更改默认语言、区域设置和其他国际设置

区域标记: zh-CN

 $\label{lem:limit} \mbox{Dism/Image:"D:\OS_11_Custom\Boot\Boot\Boot\Mount"/Set-AllIntl:zh-CN} \\$

4.2.2. 查看可用的语言设置



4.3. 语言包: 删除

- 添加语言后,如果要部署到非英语区域,可通过删除英语语言组件来节省空间。删除语言时,请按与添加语言组件相反的顺序卸载语言组件。
- 添加中文后,反向删除"英语-美国",区域: en-US,需提前提取语言包
- Boot.Del.Specified.lang.Tag.ps1
 - \Expand\Boot\Boot.Del.Specified.lang.Tag.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Boot/Boot.Del.Specified.lang.Ta g.ps1

复制代码

```
$Lang = "en-US"
$Mount = "D:\OS_11_Custom\Boot\Boot\Mount"
$Sources = "D:\OS_11_Custom\Boot\Boot\Language\Del\en-US"
$Initl_install_Language_Component = @()
Get-WindowsPackage -Path $Mount | ForEach-Object {
 $Initl_install_Language_Component += $_.PackageName
$Language = @(
 @{ Match = "*WordPad*wow64*"; File = "Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~$($Lang)~.cab"; }
 @{ Match = "*WordPad*amd64*"; File = "Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~amd64~$($Lang)~.cab"; }
 @{ Match = "*WMIC*FoD*Package*wow64*"; File = "Microsoft-Windows-WMIC-FoD-
Package~31bf3856ad364e35~wow64~$($Lang)~.cab";}
 @{ Match = "*WMIC*FoD*Package*amd64*"; File = "Microsoft-Windows-WMIC-FoD-
Package~31bf3856ad364e35~AMD64~$($Lang)~.cab";}
 @{ Match = "*StepsRecorder*wow64*"; File = "Microsoft-Windows-StepsRecorder-
Package~31bf3856ad364e35~wow64~$($Lang)~.cab";}
 @{ Match = "*StepsRecorder*amd64*"; File = "Microsoft-Windows-StepsRecorder-
Package~31bf3856ad364e35~amd64~$($Lang)~.cab";}
 @{ Match = "*Printing*PMCPPC*amd64*"; File = "Microsoft-Windows-Printing-PMCPPC-FoD-
Package~31bf3856ad364e35~AMD64~$($Lang)~.cab";}
 @{ Match = "*PowerShell*wow64*"; File = "Microsoft-Windows-PowerShell-ISE-FOD-
Package~31bf3856ad364e35~wow64~$($Lang)~.cab"; }
 @{ Match = "*PowerShell*amd64*"; File = "Microsoft-Windows-PowerShell-ISE-FOD-
Package~31bf3856ad364e35~amd64~$($Lang)~.cab"; }
 @{ Match = "*MediaPlayer*wow64*"; File = "Microsoft-Windows-MediaPlayer-Package-wow64-$($Lang).cab"; }
 @{ Match = "*MediaPlayer*amd64*"; File = "Microsoft-Windows-MediaPlayer-Package-AMD64-$($Lang).cab"; }
 @{ Match = "*Notepad*wow64*"; File = "Microsoft-Windows-Notepad-System-FoD-
```

```
Package~31bf3856ad364e35~wow64~$($Lang)~.cab";}
 @{ Match = "*Notepad*amd64*"; File = "Microsoft-Windows-Notepad-System-FoD-
Package~31bf3856ad364e35~AMD64~$($Lang)~.cab";}
 @{ Match = "*InternetExplorer*"; File = "Microsoft-Windows-InternetExplorer-Optional-
Package~31bf3856ad364e35~AMD64~$($Lang)~.cab";}
 @{ Match = "*TextToSpeech*"; File = "Microsoft-Windows-LanguageFeatures-TextToSpeech-$($Lang)-
Package~31bf3856ad364e35~amd64~~.cab"; }
 @{ Match = "*LanguageFeatures-Speech*"; File = "Microsoft-Windows-LanguageFeatures-Speech-$($Lang)-
Package~31bf3856ad364e35~amd64~~.cab"; }
 @{ Match = "*OCR*"; File = "Microsoft-Windows-LanguageFeatures-OCR-$($Lang)-Package~31bf3856ad364e35~amd64~~.cab"; }
 @{ Match = "*Handwriting*"; File = "Microsoft-Windows-LanguageFeatures-Handwriting-$($Lang)-
Package~31bf3856ad364e35~amd64~~.cab"; }
 @{ Match = "*LanguageFeatures-Basic*"; File = "Microsoft-Windows-LanguageFeatures-Basic-$($Lang)-
Package~31bf3856ad364e35~amd64~~.cab"; }
 @{ Match = "*Client-LanguagePack-Package*"; File = "Microsoft-Windows-Client-Language-Pack_x64_$($Lang).cab"; }
ForEach ($Rule in $Language) {
 Write-host "`n Rule name: $($Rule.Match)" -ForegroundColor Yellow; Write-host " $('-' * 80)"
 ForEach ($Component in $Initl_install_Language_Component) {
   if ($Component -like "*$($Rule.Match)*$($Lang)*") {
     Write-host " Component name: " -NoNewline; Write-host $Component -ForegroundColor Green
     Write-host " Language pack file: " -NoNewline; Write-host "$($Sources)\$($Rule.File)" -ForegroundColor Green
     Write-Host " Deleting ".PadRight(22) -NoNewline
     try {
       Remove-WindowsPackage -Path $Mount -PackagePath "$($Sources)\$($Rule.File)" -ErrorAction SilentlyContinue | Out-Null
      Write-host "Finish" -ForegroundColor Green
     } catch {
       Write-host "Failed" -ForegroundColor Red
      Write-host " $($_)" -ForegroundColor Red
     break
$InitlClearLanguagePackage = @()
Get-WindowsPackage -Path $Mount | ForEach-Object {
 if ($_.PackageName -like "*$($Lang)*") {
```

```
$InittClearLanguagePackage += $_.PackageName
}

if ($InittClearLanguagePackage.count -gt 0) {

ForEach ($item in $InittClearLanguagePackage) {

Write-Host "`n $($item)" -ForegroundCotor Green

Write-Host " Deleting ".PadRight(22) -NoNewline

try {

Remove-AppxProvisionedPackage -Path $Mount -PackageName $item -ErrorAction SitentlyContinue | Out-Null

Write-host "Finish" -ForegroundCotor Green

) catch {

Write-host "Failed" -ForegroundCotor Red

Write-host " $($_)" -ForegroundCotor Red

}
}
```

4.4. 组件:映像中已安装的所有包

4.4.1. 查看

Get-WindowsPackage -Path "D:\OS_11_Custom\Boot\Boot\Mount" | Out-GridView

4.4.2. 导出到 Csv

\$SaveTo = "D:\OS_11_Custom\Boot\Boot\Report.\$(Get-Date -Format "yyyyMMddHHmmss").csv"

Get-WindowsPackage -Path "D:\OS_11_Custom\Boot\Boot\Mount" | Export-CSV -NoType -Path \$SaveTo

Write-host \$SaveTo -ForegroundColor Green

4.5. 语言包: 修复

4.5.1. 提取

打开: D:\OS_11_Custom\Install\Language\Add\zh-CN\Microsoft-Windows-Client-Language-Pack_x64_zh-CN.cab, 进

入目录: Setup\sources\zh-cn\cli, 复制以下文件到桌面:

4.5.1.1. arunres.dll.mui

4.5.1.2. spwizres.dll.mui

4.5.1.3. w32uires.dll.mui

4.5.2. 复制

将提取的文件复制到: D:\OS_11_Custom\Boot\Boot\Mount\sources\zh-CN

4.6. 语言包:同步到ISO安装程序

Copy-Item -Path "D:\OS_11_Custom\Boot\Boot\Mount\sources\zh-CN" -Destination "D:\OS_11\sources\zh-CN" -Recurse -Force

4.7. 重新生成 Lang.ini

重新生成后,可调整"安装界面",选择"语言"时的顺序,打开 lang.ini,默认首选值 = 3,非默认值 = 2。

4.7.1. 重新生成已挂载目录 lang.ini

重新生成的 Lang.ini 文件位置: D:\OS_11_Custom\Boot\Boot\Mount\Sources\lang.ini

Dism /image:"D:\OS_11_Custom\Boot\Boot\Mount" /gen-langini /distribution:"D:\OS_11_Custom\Boot\Boot\Mount"

4.7.2. 重新生成 lang.ini 后,同步到安装程序

重新生成的 Lang.ini 文件位置: D:\OS_11\Sources\lang.ini

Dism /image:"D:\OS_11_Custom\Boot\Boot\Mount" /gen-langini /distribution:"D:\OS_11"

5. 累积更新

准备可用的累积更新文件,请更改示例文件名: KB_Boot.cab

5.1. 添加

 $$KBPath = "D:\OS_11_Custom\Boot\Boot\Update\KB_Boot.cab"$

Add-WindowsPackage -Path "D:\OS_11_Custom\Boot\Boot\Mount" -PackagePath \$KBPath

5.2. 删除

\$KBPath = "D:\OS_11_Custom\Boot\Boot\Update\KB_Boot.cab"

 $Remove-Windows Package - Path "D: \OS_11_Custom \Boot \Boot \Mount" - Package Path $KBPath \Boot \Bo$

5.3. 固化更新

固化后不可卸载,固化时将清理恢复映像并重置任何被取代的组件的基础。

Dism /image:"D:\OS_11_Custom\Boot\Boot\Mount" /cleanup-image /StartComponentCleanup /ResetBase

5.3.1. 固化更新后清理组件

```
$Mount = "D:\OS_11_Custom\Boot\Boot\Mount"

Get-WindowsPackage -Path $Mount -ErrorAction SilentlyContinue | ForEach-Object {

if ($_.PackageState -eq "Superseded") {

Write-Host " $($_.PackageName)" -ForegroundColor Green

Remove-WindowsPackage -Path $Mount -PackageName $_.PackageName | Out-Null
}
```

6. 驱动

7. 其它

7.1. 绕过 TPM 安装时检查

- Boot.Bypass.TPM.ps1
 - \Expand\Boot\Boot.Bypass.TPM.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/Boot/Boot.Bypass.TPM.ps1

复制代码

 $RegSystem = "D:\OS_11_Custom\Boot\Boot\Mount\Windows\System32\Config\SYSTEM"$

\$RandomGuid = [guid]::NewGuid()

Write-Host " HKLM:\\$(\$RandomGuid)"

New-PSDrive -PSProvider Registry -Name OtherTasksTPM -Root HKLM -ErrorAction SilentlyContinue | Out-Null

Start-Process reg -ArgumentList "Load ""HKLM\\$(\$RandomGuid)"" ""\$(\$RegSystem)""" -Wait -WindowStyle Hidden -ErrorAction SilentlyContinue

New-Item "HKLM:\\$(\$RandomGuid)\Setup\LabConfig" -force -ea SilentlyContinue | Out-Null

New-ItemProperty -LiteralPath "HKLM:\\$(\$RandomGuid)\Setup\LabConfig" -Name "BypassCPUCheck" -Value 1 -PropertyType DWord -Force -ea SilentlyContinue | Out-Null

New-ItemProperty -LiteralPath "HKLM:\\$(\$RandomGuid)\Setup\LabConfig" -Name "BypassStorageCheck" -Value 1 -PropertyType DWord -Force -ea SilentlyContinue | Out-Null

New-ItemProperty -LiteralPath "HKLM:\\$(\$RandomGuid)\Setup\LabConfig" -Name "BypassRAMCheck" -Value 1 -PropertyType DWord -Force -ea SilentlyContinue | Out-Null

New-ItemProperty -LiteralPath "HKLM:\\$(\$RandomGuid)\Setup\LabConfig" -Name "BypassTPMCheck" -Value 1 -PropertyType DWord -Force -ea SilentlyContinue | Out-Null

New-ItemProperty -LiteralPath "HKLM:\\$(\$RandomGuid)\Setup\LabConfig" -Name "BypassSecureBootCheck" -Value 1 -PropertyType DWord -Force -ea SilentlyContinue | Out-Null

[gc]::collect()

 $Start-Process\ reg\ -Argument List\ "unload\ ""HKLM\ (\$RandomGuid)"""\ -Wait\ -WindowStyle\ Hidden\ -ErrorAction\ Silently Continue$



8. 保存映像: Boot.wim

Save-WindowsImage -Path "D:\OS_11_Custom\Boot\Boot\Mount"

9. 卸载映像: Boot.wim

关闭所有可能正在访问映像中文件的应用程序,包括文件资源管理器。

Dismount-WindowsImage -Path "D:\OS_11_Custom\Boot\Boot\Mount" -Discard

Ⅳ 部署引擎

- 了解"自动添加 Windows 系统已安装的语言",学习:https://github.com/ilikeyi/Multilingual,如何下载:
 - 进入网站后,点击"代码","下载压缩包",下载完成后得到 main.zip 压缩包文件。
 - 前往 https://github.com/ilikeyi/Multilingual/releases 下载页面,选择可用版本:1.1.1.1,选择下载源代码格式:zip,下载完成后得到Multilingual-1.1.1.1.zip 压缩包文件;
- 将已下载的 main.zip 或 Multilingual-1.1.1.1.zip,解压到:D:\Multilingual-1.1.1.1,重命名:D:\Multilingual
- 学习"无人值守 Windows 安装参考",通过无人值守来干预安装过程。
- 1. 添加方式
 - 1.1. 添加到 ISO 安装介质
 - 1.1.1. 无人值守
 - 1.1.1.1. 添加到: [ISO]:\Autounattend.xml

引导 ISO 安装时,Autounattend.xml 干预 WinPE 安装程序。

复制 D:\Multilingual_Learn\Unattend\Mul.Unattend.xml 到 D:\OS_11\Autounattend.xml

Copy-Item "D:\Multilingual_Learn\Unattend\Mul.Unattend.xml" -Destination "D:\OS_11\Autounattend.xml" -Force

1.1.1.2. 添加到: [ISO]:\Sources\Unattend.xml

挂载或解压 ISO 时,运行 [ISO]:\Setup.exe 安装程序后,[ISO]:\Sources\Unattend.xml 将干预安装过程。

复制 D:\Multilingual_Learn\Unattend\Mul.Unattend.xml 到 D:\OS_11\Sources\Unattend.xml

 $\label{lem:copy-lem$

1.1.1.3. 添加到: [ISO]:\sources\\$OEM\$\\$\$\Panther\unattend.xml

安装过程中复制到系统盘里,复制到: {系统盘}:\Windows\Panther\unattend.xml

1.1.1.3.1. 创建 \$OEM\$ 路径

New-Item -Path "D:\OS_11\sources\` \$OEM\$\` \$\$\Panther" -ItemType Directory

1.1.1.3.2. 复制

复制 D:\Multilingual_Learn\Unattend\Mul.Unattend.xml 到

D:\OS_11\Sources\\$OEM\$\Panther\Unattend.xml

Copy-Item "D:\Multilingual_Learn\Unattend\Mul.Unattend.xml" -Destination "D:\OS_11\sources\`\$OEM\$\`\$\$\Panther\Unattend.xml" -Force

1.1.2. 部署引擎:添加

添加"自动添加 Windows 系统已安装的语言"到 D:\OS_11\sources\\$OEM\$\\$1\Yi\Engine 目录里。

1.1.2.1. 部署引擎: 复制

复制 D:\Multilingual\Engine 到 D:\OS_11\Sources\\$OEM\$\\$1\Yi\Engine

Copy-Item "D:\Multilingual\Engine" -Destination "D:\OS_11\sources\` \$OEM\$\` \$1\Yi\Engine" -Recurse -Force

1.1.2.2. 部署引擎: 自定义部署标记

\$Flag = @(

"Is_Mark_Sync" # 允许全盘搜索并同步部署标记

- # 先决部署
- # "Auto_Update" # 允许自动更新
- # "Use_UTF8" # Beta 版:使用 Unicode UTF-8 提供全球语言支持

"Disable_Network_Location_Wizard" # 网络位置向导

"Disable_Cleanup_Appx_Tasks" # Appx 清理维护任务

"Disable_Cleanup_On_Demand_Language" # 阻止清理未使用的按需功能语言包

"Disable_Cleanup_Unsed_Language" # 阻止清理未使用的语言包

"Prerequisites_Reboot" # 重新启动计算机

#完成首次部署



```
# "Popup_Engine" # 允许首次弹出部署引擎主界面

# "Allow_First_Pre_Experience" # 允许首次预体验,按计划

"Reset_Execution_Policy" # 恢复 PowerShell 执行策略:受限

"Clear_Solutions" # 删除整个解决方案

"Clear_Engine" # 删除部署引擎,保留其它

# "First_Experience_Reboot" # 重新启动计算机
)

ForEach ($item in $Flag) {

Write-host" $($item)" -ForegroundColor Green

New-Item -Path "D:\OS_11\sources\`$OEM$\`$1\Yi\Engine\Deploy\Allow" -ItemType Directory -ErrorAction
SilentlyContinue | Out-Null

Out-File -FilePath "D:\OS_11\sources\`$OEM$\`$1\Yi\Engine\Deploy\Allow\$($item)" -Encoding utf8 -
```

1.2. 添加到已挂载

通过"自定义封装: Install.wim",执行"开始挂载 Install.wim",挂载到: D:\OS_11_Custom\Install\Install\Mount

ErrorAction SilentlyContinue

1.2.1. 无人值守

复制 D:\Multilingual_Learn\Unattend\Mul.Unattend.xml 到 D:\OS_11_Custom\Install\Install\Mount\Panther\Unattend.xml

Copy-Item "D:\Multilingual_Learn\Unattend\Mul.Unattend.xml" -Destination "D:\OS_11_Custom\Install\Install\Mount\Panther" -Force

1.2.2. 部署引擎

添加"自动添加 Windows 系统已安装的语言"到 D:\OS_11_Custom\Install\Install\Mount\Yi\Engine 目录里。

1.2.2.1. 部署引擎: 复制

复制 D:\Multilingual\Engine 到 D:\OS_11_Custom\Install\Install\Mount\Yi\Engine

1.2.2.2. 部署引擎: 自定义部署标记

\$Flag = @(



```
"Is_Mark_Sync" # 允许全盘搜索并同步部署标记
       # 先决部署
# "Auto_Update" # 允许自动更新
# "Use_UTF8" # Beta 版:使用 Unicode UTF-8 提供全球语言支持
       "Disable_Network_Location_Wizard" # 网络位置向导
        "Disable_Cleanup_Appx_Tasks" # Appx 清理维护任务
       "Disable_Cleanup_On_Demand_Language" # 阻止清理未使用的按需功能语言包
        "Disable_Cleanup_Unsed_Language" # 阻止清理未使用的语言包
        "Prerequisites_Reboot" # 重新启动计算机
       #完成首次部署
 # "Popup_Engine" # 允许首次弹出部署引擎主界面
# "Allow_First_Pre_Experience" # 允许首次预体验,按计划
       "Reset_Execution_Policy" # 恢复 PowerShell 执行策略: 受限
       "Clear_Solutions"#删除整个解决方案
        "Clear_Engine" # 删除部署引擎,保留其它
# "First_Experience_Reboot" # 重新启动计算机
ForEach ($item in $Flag) {
       Write-host " $($item)" -ForegroundColor Green
       New-Item-Path "D: \OS\_11\_Custom \Install \Mount \Yi \Engine \Deploy \Allow "-Item Type Directory-Item Ty
ErrorAction SilentlyContinue | Out-Null
      Out-File - File Path "D: \OS\_11\_Custom \Install \Mount \Yi\Engine \Deploy \Allow \$(\$item)" - Encoding utf8-line \Allow \Allow
ErrorAction SilentlyContinue
```

2. 部署引擎:进阶

2.1. 部署引擎:添加过程中

在复制部署引擎后,可添加部署标记来干预安装过程。

2.2. 无人值守方案

自定义无人值守时,以下文件存在时请同步修改:



- D:\OS_11\Autounattend.xml
- D:\OS_11\Sources\Unattend.xml
- D:\OS_11\sources\\$OEM\$\\$\$\Panther\unattend.xml
- D:\OS_11_Custom\Install\Install\Mount\Panther\Unattend.xml

2.2.1. 多语言或单语

多语言时,单语时,可互相切换,替换时,请替换文件里所有相同的。

2.2.1.1. 多语言

- <UILanguage>%OSDUILanguage%</UILanguage>
- <InputLocale>%OSDInputLocale%</InputLocale>
- <SystemLocale>%OSDSystemLocale%</SystemLocale>
- UILanguage>%OSDUILanguage%</UILanguage>
- <UILanguageFallback>%OSDUILanguageFallback%</UILanguageFallback>
- <UserLocale>%OSDUserLocale%</UserLocale>

2.2.1.2. 单语

单语需指定区域,例如指定区域: zh-CN

- <UILanguage>zh-CN</UILanguage>
- <InputLocale>zh-CN</InputLocale>
- $<\!SystemLocale\!\!>\!zh\text{-}CN<\!/SystemLocale\!\!>$
- <UILanguage>zh-CN</UILanguage>
- <UILanguageFallback>zh-CN</UILanguageFallback>
- <userLocale>zh-CN</userLocale>

2.2.2. 用户方案

默认使用自建用户 Administrator 并自动登录,可通过修改以下配置切换:自建、自定义用户。

2.2.2.1. 自建用户 Administrator

默认使用自建用户: Administrator并自动登录,插入到 <OOBE> 和 </OOBE> 之间。

<UserAccounts>

<LocalAccounts>

<LocalAccount wcm:action="add">



```
<Password>
      <Value></Value>
      <PlainText>true</PlainText>
     </Password>
     <Description>Administrator</Description>
     <DisplayName>Administrator</DisplayName>
     <Group>Administrators</Group>
     <Name>Administrator</Name>
   </LocalAccount>
 </LocalAccounts>
</UserAccounts>
<AutoLogon>
 <Password>
   <Value></Value>
   <PlainText>true</PlainText>
  </Password>
  <Enabled>true</Enabled>
 <use><Username>Administrator</Username>
</AutoLogon>
```

2.2.2.2. 自定义用户

设置自定义用户后,安装系统完成后,在 OOBE 里,可选择本地、在线用户等设置。

2.2.2.2.1. 删除

用户名:从开始处删除 <UserAccounts> 到 </UserAccounts>

自动登录:从开始处删除 < AutoLogon > 到 < / AutoLogon >

2.2.2.2.2. 替换

从开始处 <OOBE> 到 </OOBE>

<OOBE>

<ProtectYourPC>3</ProtectYourPC>

<HideEULAPage>true</HideEULAPage>

 $<\!HideWirelessSetupInOOBE\!>\!true<\!/HideWirelessSetupInOOBE\!>$

D. ISO

- Ⅱ 生成 ISO
 - 1. 下载 OScdimg

根据架构选择 Oscdimg 版本,下载后保存到:D:\, 保存在其它路径请输入 OScdimg.exe 绝对路径;

1.1. x64

https://github.com/ilikeyi/solutions/raw/main/_Software/Oscdimg/amd64/oscdimg.exe

1.2. x86

https://github.com/ilikeyi/solutions/raw/main/_Software/Oscdimg/x86/oscdimg.exe

1.3. arm64

https://github.com/ilikeyi/solutions/raw/main/_Software/Oscdimg/arm64/oscdimg.exe

- 2. 使用 oscdimg 命令行生成一个 ISO 文件,保存到:D:\Win11.iso
 - ISO.ps1
 - o \Expand\ISO.ps1
 - o https://github.com/ilikeyi/solutions/blob/main/_Learn/Packaging.tutorial/OS.11/23H2/Expand/ISO.ps1
 - 复制代码

```
$Oscdimg = "D:\Oscdimg.exe"

$ISO = "D:\OS_11"

$Volume = "OS_11"

$SaveTo = "D:\OS_11.iso"

$Arguments = @("-m", "-o", "-u2", "-udfver102", "-l""$($Volume)""", "-
bootdata:2#p0,e,b""$($ISO)\boot\etfsboot.com""#pEF,e,b""$($ISO)\efi\microsoft\boot\efisys.bin""", $ISO, $SaveTo)

Start-Process -FilePath $Oscdimg -ArgumentList $Arguments -wait -nonewwindow
```

III 绕过 TPM 安装检查

- 1. 了解 https://github.com/AveYo/MediaCreationTool.bat/tree/main/bypass11 并下载: Quick_11_iso_esd_wim_TPM_toggle.bat
- 2. 将 D:\OS_11.iso 文件托到 Quick_11_iso_esd_wim_TPM_toggle.bat 里,反序"添加"或"删除"TPM 安装时检查功能。

章节2 报告

编组缩写:

- **群组 A:** Windows 11 教育版、Windows 11 企业版、Windows 11 专业版、Windows 11 专业版首版、Windows 11 专业版工作站、Windows 11 专业版 loT 企业版
- 群组 B:Windows 11 教育版 N、Windows 11 企业版 N、Windows 11 专业版 N、Windows 11 专业教育版 N、Windows 11 专业版工作站 N
- 群组 C: Windows 11 家庭版、Windows 11 家庭单语版
- 群组 D: Windows 11 家庭版 N

|| 不同版本

1.	Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~~10.0.22621.382	A, C
	Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~en-US~10.0.22621.317	
2.	Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~~10.0.22621.1	A, C
	Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~en-US~10.0.22621.1	
3.	Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	А, В
4.	Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~en-US~10.0.22621.1	
5.	Microsoft-OneCore-ApplicationModel-Sync-Desktop-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.317	A, B, C, D
6.	Microsoft-OneCore-DirectX-Database-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
7.	Microsoft-Windows-Client-LanguagePack-Package~31bf3856ad364e35~amd64~en-US~10.0.22621.382	A, B, C, D
8.	Microsoft-Windows-Ethernet-Client-Intel-E1i68x64-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
9.	Microsoft-Windows-Ethernet-Client-Intel-E2f68-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
10.	Microsoft-Windows-Ethernet-Client-Realtek-Rtcx21x64-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
11.	Microsoft-Windows-Ethernet-Client-Vmware-Vmxnet3-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
12.	Microsoft-Windows-FodMetadata-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
13.	Microsoft-Windows-Foundation-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
14.	Microsoft-Windows-Hello-Face-Package~31bf3856ad364e35~amd64~~10.0.22621.317	A, B, C, D
15.	Microsoft-Windows-InternetExplorer-Optional-Package~31bf3856ad364e35~amd64~~11.0.22621.1	A, B, C, D
	Microsoft-Windows-InternetExplorer-Optional-Package~31bf3856ad364e35~amd64~en-US~11.0.22621.1	A, B, C, D
16.	Microsoft-Windows-Kernel-LA57-FoD-Package~31bf3856ad364e35~amd64~~10.0.22621.382	A, B, C, D
17.	Microsoft-Windows-LanguageFeatures-Basic-en-us-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
18.	Microsoft-Windows-LanguageFeatures-Handwriting-en-us-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
19.	Microsoft-Windows-LanguageFeatures-OCR-en-us-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
20.	Microsoft-Windows-LanguageFeatures-Speech-en-us-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
21.	Microsoft-Windows-LanguageFeatures-TextToSpeech-en-us-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D

22.	Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
	Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~amd64~en-US~10.0.22621.1	A, B, C, D
23.	Microsoft-Windows -Notepad-System-FoD-Package~31bf3856ad364e35~wow64~~10.0.22621.1	A, B, C, D
	Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~wow64~en-US~10.0.22621.1	A, B, C, D
24.	Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
	Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~amd64~en-US~10.0.22621.1	A, B, C, D
25.	Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~wow64~~10.0.22621.1	A, B, C, D
	Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~wow64~en-US~10.0.22621.1	A, B, C, D
26.	Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
	Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~amd64~en-US~10.0.22621.1	A, B, C, D
27.	Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~wow64~~10.0.22621.1	A, B, C, D
	Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~wow64~en-US~10.0.22621.1	A, B, C, D
28.	Microsoft-Windows-TabletPCMath-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
29.	Microsoft-Windows-Wallpaper-Content-Extended-FoD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
30.	Microsoft-Windows-Wifi-Client-Broadcom-Bcmpciedhd63-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
31.	Microsoft-Windows-Wifi-Client-Broadcom-Bcmwl63a-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
32.	Microsoft-Windows-Wifi-Client-Broadcom-Bcmwl63al-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
33.	Microsoft-Windows-Wifi-Client-Intel-Netwbw02-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
34.	Microsoft-Windows-Wifi-Client-Intel-Netwew00-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
35.	Microsoft-Windows-Wifi-Client-Intel-Netwew01-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
36.	Microsoft-Windows-Wifi-Client-Intel-Netwlv64-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
37.	Microsoft-Windows-Wifi-Client-Intel-Netwns64-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
38.	Microsoft-Windows-Wifi-Client-Intel-Netwsw00-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
39.	Microsoft-Windows-Wifi-Client-Intel-Netwtw02-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
40.	Microsoft-Windows-Wifi-Client-Intel-Netwtw04-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
41.	Microsoft-Windows-Wifi-Client-Intel-Netwtw06-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
42.	Microsoft-Windows-Wifi-Client-Intel-Netwtw08-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
43.	Microsoft-Windows-Wifi-Client-Intel-Netwtw10-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
44.	Microsoft-Windows-Wifi-Client-Marvel-Mrvlpcie8897-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
45.	Microsoft-Windows-Wifi-Client-Qualcomm-Athw8x-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
46.	Microsoft-Windows-Wifi-Client-Qualcomm-Athwnx-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
47.	Microsoft-Windows-Wifi-Client-Qualcomm-Qcamain10x64-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
48.	Microsoft-Windows-Wifi-Client-Ralink-Netr28x-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
49.	Microsoft-Windows-Wifi-Client-Realtek-Rtl8187se-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D

50.	Microsoft-Windows-Wifi-Client-Realtek-Rtl8192se-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
51.	Microsoft-Windows-Wifi-Client-Realtek-Rtl819xp-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
52.	Microsoft-Windows-Wifi-Client-Realtek-Rtl85n64-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
53.	Microsoft-Windows-Wifi-Client-Realtek-Rtwlane-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
54.	Microsoft-Windows-Wifi-Client-Realtek-Rtwlane01-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
55.	Microsoft-Windows-Wifi-Client-Realtek-Rtwlane13-FOD-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
56.	Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~amd64~~10.0.22621.382	A, B, C, D
	Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~amd64~en-US~10.0.22621	A, B, C, D
57.	Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~wow64~~10.0.22621.1	A, B, C, D
	Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~wow64~en-US~10.0.22621.1	A, B, C, D
58.	Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~amd64~~10.0.22621.317	A, B, C, D
	Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~amd64~en-US~10.0.22621.1	A, B, C, D
59.	Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~~10.0.22621.1	A, B, C, D
	Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~en-US~10.0.22621.1	A, B, C, D
60.	OpenSSH-Client-Package~31bf3856ad364e35~amd64~~10.0.22621.1	A, B, C, D
61.	Package_for_DotNetRollup_481~31bf3856ad364e35~amd64~~10.0.9065.6	A, B, C, D
62.	Package_for_RollupFix~31bf3856ad364e35~amd64~~22621.382.1.13	A, B, C, D
63.	Package_for_ServicingStack_378~31bf3856ad364e35~amd64~~22621.378.1.0	A, B, C, D
63.	Package_for_ServicingStack_378~31bf3856ad364e35~amd64~~22621.378.1.0	A, B, C, D
	Package_for_ServicingStack_378~31bf3856ad364e35~amd64~~22621.378.1.0 安装包适用于:Install.wim	A, B, C, D
		A, B, C, D A, C
语言	安装包适用于:Install.wim	
语言	安装包适用于:Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab	
语言 1.	安装包适用于:Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	A, C
语言 1.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab	A, C
语言 1. 2.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1	A, C
语言 1. 2.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1 Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab	A, C
语言 1. 2.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1 Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	A, C A, C
语言 1. 2.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1 Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	A, C A, C
语言 1. 2.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1 Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-LanguageFeatures-Fonts-Hans-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	A, C A, C A, B
语言 1. 2.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1 Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-LanguageFeatures-Fonts-Hans-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-LanguageFeatures-Fonts-Hans-Package~31bf3856ad364e35~amd64~~10.0.22621.1 Microsoft-Windows-Client-Language-Pack_x64_zh-CN.cab	A, C A, C A, B
语言 1. 2. 4.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1 Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-LanguageFeatures-Fonts-Hans-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-LanguageFeatures-Fonts-Hans-Package~31bf3856ad364e35~amd64~~10.0.22621.1 Microsoft-Windows-Client-Language-Pack_x64_zh-CN.cab Microsoft-Windows-Client-LanguagePack-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	A, C A, C A, B A, B, C, D
语言 1. 2. 4.	安装包适用于: Install.wim Microsoft-Windows-MediaPlayer-Package-AMD64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package-31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-MediaPlayer-Package-wow64-zh-CN.cab Microsoft-Windows-MediaPlayer-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1 Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab Microsoft-Windows-Printing-PMCPPC-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-LanguageFeatures-Fonts-Hans-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-LanguageFeatures-Fonts-Hans-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-Client-Language-Pack_x64_zh-CN.cab Microsoft-Windows-Client-LanguagePack-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1 Microsoft-Windows-InternetExplorer-Optional-Package~31bf3856ad364e35~AMD64~zh-CN~.cab	A, C A, C A, B A, B, C, D

Ш

8.	Microsoft-Windows-LanguageFeatures-Handwriting-zh-CN-Package~31bf3856ad364e35~AMD64~~.cab	A, B, C, D
	Microsoft-Windows-LanguageFeatures-Handwriting-zh-cn-Package~31bf3856ad364e35~amd64~~10.0.22621.1	
9.	Microsoft-Windows-LanguageFeatures-OCR-zh-CN-Package~31bf3856ad364e35~AMD64~~.cab	A, B, C, D
	Microsoft-Windows-LanguageFeatures-OCR-zh-cn-Package~31bf3856ad364e35~amd64~~10.0.22621.1	
10.	Microsoft-Windows-LanguageFeatures-Speech-zh-CN-Package~31bf3856ad364e35~AMD64~~.cab	A, B, C, D
	Microsoft-Windows-LanguageFeatures-Speech-zh-cn-Package~31bf3856ad364e35~amd64~~10.0.22621.1	
11.	Microsoft-Windows-LanguageFeatures-TextToSpeech-zh-CN-Package~31bf3856ad364e35~AMD64~~.cab	A, B, C, D
	Microsoft-Windows-LanguageFeatures-TextToSpeech-zh-cn-Package~31bf3856ad364e35~amd64~~10.0.22621.1	
12.	Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	
13.	Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~wow64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-Notepad-System-FoD-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1	
14.	Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	
15.	Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~wow64~zh-CN~.cab	
	Microsoft-Windows-PowerShell-ISE-FOD-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1	
16.	Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~AMD64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	
17.	Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~wow64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-StepsRecorder-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1	
18.	Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	
19.	Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~wow64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-WMIC-FoD-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1	
20.	Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~AMD64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1	
21.	Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~zh-CN~.cab	A, B, C, D
	Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1	

IV 语言安装包适用于: WinRE.wim

1. WinPE-FontSupport-zh-CN.cab

Microsoft-Windows-WinPE-FontSupport-ZH-CN-Package ~31bf3856ad364e35 ~amd64 ~~10.0.22621.1

Microsoft-Windows-WordPad-FoD-Package~31bf3856ad364e35~wow64~zh-CN~10.0.22621.1

2. lp.cab

 $Microsoft-Windows-WinPE-Language Pack-Package {\tt ~31bf3856ad364e35} {\tt ~amd64~zh-CN~10.0.22621.1}$

3. winpe-appxdeployment_zh-CN.cab

WinPE-AppxDeployment-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

4. winpe-appxpackaging_zh-CN.cab

 $Win PE-Appx Packaging-Package \sim 31bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

5. winpe-atbroker_zh-CN.cab

WinPE-ATBroker-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

6. winpe-audiocore_zh-CN.cab

WinPE-AudioCore-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

7. winpe-audiodrivers_zh-CN.cab

 $Win PE-Audio Drivers-Package \sim 31bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

8. winpe-enhancedstorage_zh-CN.cab

WinPE-EnhancedStorage-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

9. winpe-hta_zh-CN.cab

WinPE-HTA-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

10. winpe-narrator_zh-CN.cab

WinPE-Narrator-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

11. winpe-opcservices_zh-CN.cab

 $Win PE-Opc Services-Package \sim 31bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

12. winpe-rejuv_zh-CN.cab

 $Win PE-Rejuv-Package {\footnotesize \sim} 31bf 3856 ad 364 e 35 {\footnotesize \sim} amd 64 {\footnotesize \sim} zh-CN {\footnotesize \sim} 10.0.22621.1$

13. winpe-scripting_zh-CN.cab

 $Win PE-Scripting-Package \sim 31bf3856ad364e35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

14. winpe-securestartup_zh-CN.cab

 $Win PE-Secure Startup-Package \sim 31bf 3856 ad 364e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

15. winpe-speech-tts_zh-CN.cab

 $Win PE-Speech-TTS-Package {\tt ~31bf3856} ad 364e 35 {\tt ~amd64 {\tt ~zh-CN {\tt ~10.0.22621.1}}$

16. winpe-srh_zh-CN.cab

 $Win PE-SRH-Package {\sim} 31 bf 3856 ad 364 e 35 {\sim} amd 64 {\sim} zh-CN {\sim} 10.0.22621.1$

17. winpe-srt_zh-CN.cab

 $Win PE-SRT-Package {\sim} 31 bf 3856 ad 364 e 35 {\sim} amd 64 {\sim} zh-CN {\sim} 10.0.22621.1$

18. winpe-storagewmi_zh-CN.cab

 $Win PE-Storage WMI-Package {\tt ~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1}$

19. winpe-wds-tools_zh-CN.cab

 $Win PE-WDS-Tools-Package \sim 31bf 3856 ad 364e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

20. winpe-wifi_zh-CN.cab

 $Win PE-WiFi-Package \sim 31bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

21. winpe-windowsupdate_zh-CN.cab

 $Win PE-Windows Update-Package \sim 31 bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

22. winpe-wmi_zh-CN.cab

 $Win PE-WMI-Package \sim 31 bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

V 语言安装包适用于: Boot.wim

1. WinPE-FontSupport-zh-CN.cab

 $Microsoft-Windows-WinPE-FontSupport-ZH-CN-Package {\tt ~31bf3856ad364e35~amd64~~10.0.22621.1}$

2. lp.cab

Microsoft-Windows-WinPE-LanguagePack-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

3. winpe-atbroker_zh-CN.cab

 $Win PE-AT Broker-Package \sim 31 bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

4. winpe-audiocore_zh-CN.cab

WinPE-AudioCore-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

5. winpe-audiodrivers_zh-CN.cab

WinPE-AudioDrivers-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

6. winpe-enhancedstorage_zh-CN.cab

 $Win PE-Enhanced Storage-Package {\tt ~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1}$

7. winpe-narrator_zh-CN.cab

 $Win PE-Narrator-Package {\footnotesize \sim} 31bf3856ad364e35 {\footnotesize \sim} amd64 {\footnotesize \sim} zh-CN {\footnotesize \sim} 10.0.22621.1$

8. winpe-scripting_zh-CN.cab

 $Win PE-Scripting-Package \sim 31bf 3856 ad 364e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

9. winpe-securestartup_zh-CN.cab

 $Win PE-Secure Startup-Package {\tt ~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1}$

10. WINPE-SETUP-CLIENT_zh-CN.CAB

 $Win PE-Setup-Client-Package \sim 31bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.11$

11. WinPE-Setup_zh-CN.cab

WinPE-Setup-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

12. winpe-speech-tts_zh-CN.cab

 $Win PE-Speech-TTS-Package \sim 31bf 3856 ad 364e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

13. winpe-srh_zh-CN.cab

WinPE-SRH-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

14. winpe-srt_zh-CN.cab

 $Win PE-SRT-Package \sim 31bf 3856 ad 364 e 35 \sim amd 64 \sim zh-CN \sim 10.0.22621.1$

15. winpe-wds-tools_zh-CN.cab

 $Win PE-WDS-Tools-Package {\tt ~31bf3856} ad 364e 35 {\tt ~amd64~zh-CN~10.0.22621.1}$

16. winpe-wmi_zh-CN.cab

WinPE-WMI-Package~31bf3856ad364e35~amd64~zh-CN~10.0.22621.1

章节3 常见问题

II 清理所有挂载到

关闭所有可能正在访问映像中文件的应用程序,包括文件资源管理器。

 $\label{lem:linear_lin$

 $\label{lem:linear_lin$

Dismount-WindowsImage -Path "D:\OS_11_Custom\Boot\Boot\Mount" -Discard

Ⅲ 修复挂载出现异常的问题

1. 查看已挂载

Get-WindowsImage -Mounted

2. 删除保存在注册表里的 DISM 挂载记录

Remove-Item -Path "HKLM:\SOFTWARE\Microsoft\WIMMount\Mounted Images*" -Force -Recurse -ErrorAction SilentlyContinue | Out-Null

3. 删除与已损坏的已装载映像关联的所有资源。

 ${\bf Clear\text{-}WindowsCorruptMountPoint}$

Dism /cleanup-wim

Ⅳ 清理目录

Remove-Item "D:\OS_11_Custom" -Force -Recurse

 $Remove-Item "D: \OS_11 \setminus Sources \` \$OEM\$" - Force - Recurse$

Remove-Item -Path "D:\OS_11\Autounattend.xml" -Force

 $Remove-Item\ -Path\ "D:\OS_11\Sources\Unattend.xml"\ -Force$

章节4 已知问题

暂无



此副本封装教程隶属于 Yi's Solutions 内容, 学习更多:

- Yi 的官方网站 | https://fengyi.tel/solutions
- Github | https://github.com/ilikeyi/solutions

作者: Yi

邮箱: 775159955@qq.com, ilikeyi@outlook.com

文档版本: 1.1

文档模型: 完整版

更新日期: 2024-6

建议或反馈: https://github.com/ilikeyi/solutions/issues